Inside: Racket C API

Version 5.3.4

Matthew Flatt

May 8, 2013

This manual describes Racket's C interface, which allows the interpreter to be extended by a dynamically-loaded library, or embedded within an arbitrary C/C++ program. The manual assumes familiarity with Racket as described in *The Racket Reference*.

For an alternative way of dealing with foreign code, see *The Racket Foreign Interface*, which describes the ffi/unsafe module for manipulating low-level libraries and structures purely through Racket code.

Contents

1	Ove	rview	5
	1.1	"Scheme" versus "Racket"	5
	1.2	Building Racket from Source	5
	1.3	CGC versus 3m	5
	1.4	Writing Racket Extensions	5
		1.4.1 CGC Extensions	6
		1.4.2 3m Extensions	8
		1.4.3 Declaring a Module in an Extension	9
	1.5	Embedding Racket into a Program	10
		1.5.1 CGC Embedding	10
		1.5.2 3m Embedding	13
	1.6	Racket and Places	15
	1.7	Racket and Threads	16
	1.8	Racket, Unicode, Characters, and Strings	16
	1.9	Integers	17
•	X 7-1		10
2	valu	ies and Types	18
	2.1	Standard Types	19
	2.2	Global Constants	22
	2.3	Strings	22
	2.4	Value Functions	23
3	Men	nory Allocation	31
-			-
	3.1	Cooperating with 3m	32
		3.1.1 Tagged Objects	33

		3.1.2 Local Pointers	34
		3.1.3 Local Pointers and raco ctoolxform	38
		3.1.4 Guiding raco ctoolxform	39
		3.1.5 Places and Garbage Collector Instances	41
	3.2	Memory Functions	41
4	Nan	nespaces and Modules	51
5	Proc	cedures	54
6	Eva	luation	57
	6.1	Top-level Evaluation Functions	57
	6.2	Tail Evaluation	57
	6.3	Multiple Values	58
	6.4	Evaluation Functions	59
7	Exc	eptions and Escape Continuations	63
	7.1	Temporarily Catching Error Escapes	64
	7.2	Enabling and Disabling Breaks	67
	7.3	Exception Functions	67
8	Thr	eads	73
	8.1	Integration with Threads	73
	8.2	Allowing Thread Switches	74
	8.3	Blocking the Current Thread	74
	8.4	Threads in Embedded Racket with Event Loops	75
		8.4.1 Callbacks for Blocked Threads	76
	8.5	Sleeping by Embedded Racket	78

	8.6 Thread Functions	79
9	Parameterizations	86
10	Continuation Marks	90
11	String Encodings	91
12	Bignums, Rationals, and Complex Numbers	96
13	Ports and the Filesystem	99
14	Structures	116
15	Security Guards	119
16	Custodians	120
17	Subprocesses	123
18	Miscellaneous Utilities	124
19	Flags and Hooks	130
Inc	dex	132
Inc	dex	132

1 Overview

1.1 "Scheme" versus "Racket"

The old name for Racket was "PLT Scheme," and the core compiler and run-time system used to be called "MzScheme." The old names are entrenched in Racket internals, to the point that most C bindings defined in this manual start with scheme_. They all should be renamed to start racket_.

1.2 Building Racket from Source

The normal Racket distribution includes ".rkt" sources for collection-based libraries. After modifying library files, run raco setup (see §9 "raco setup: Installation Management") to rebuild installed libraries.

The normal Racket distribution does not include the C sources for Racket's run-time system. To build Racket from scratch, download a source distribution, or get the latest from the git repository at https://github.com/plt/racket. Detailed build instructions are in the "README" file in the top-level "src" directory.

1.3 CGC versus 3m

Before mixing any C code with Racket, first decide whether to use the **3m** variant of Racket, the **CGC** variant of Racket, or both:

- **3m** : the main variant of Racket, which uses *precise* garbage collection instead of conservative garbage collection, and it may move objects in memory during a collection.
- **CGC** : the original variant of Racket, where memory management depends on a *conservative* garbage collector. The conservative garbage collector can automatically find references to managed values from C local variables and (on some platforms) static variables.

At the C level, working with CGC can be much easier than working with 3m, but overall system performance is typically better with 3m.

1.4 Writing Racket Extensions

The process of creating an extension for 3m or CGC is essentially the same, but the process for 3m is most easily understood as a variant of the process for CGC.

1.4.1 CGC Extensions

To write a C/C++-based extension for Racket CGC, follow these steps:

• For each C/C++ file that uses Racket library functions, #include the file "escheme.h".

This file is distributed with the Racket software in an "include" directory, but if raco ctool is used to compile, this path is found automatically.

• Define the C function scheme_initialize, which takes a Scheme_Env* namespace (see §4 "Namespaces and Modules") and returns a Scheme_Object* Racket value.

This initialization function can install new global primitive procedures or other values into the namespace, or it can simply return a Racket value. The initialization function is called when the extension is loaded with load-extension the first time in a given place; the return value from scheme_initialize is used as the return value for load-extension. The namespace provided to scheme_initialize is the current namespace when load-extension is called.

• Define the C function scheme_reload, which has the same arguments and return type as scheme_initialize.

This function is called if load-extension is called a second time (or more times) for an extension in a given place. Like scheme_initialize, the return value from this function is the return value for load-extension.

• Define the C function scheme_module_name, which takes no arguments and returns a Scheme_Object* value, either a symbol or scheme_false.

The function should return a symbol when the effect of calling scheme_initialize and scheme_reload is only to declare a module with the returned name. This function is called when the extension is loaded to satisfy a require declaration.

The scheme_module_name function may be called before scheme_initialize and scheme_reload, after those functions, or both before and after, depending on how the extension is loaded and re-loaded.

• Compile the extension C/C++ files to create platform-specific object files.

The raco ctool compiler, which is distributed with Racket, compiles plain C files when the --cc flag is specified. More precisely, raco ctool does not compile the files itself, but it locates a C compiler on the system and launches it with the appropriate compilation flags. If the platform is a relatively standard Unix system, a Windows system with either Microsoft's C compiler or gcc in the path, or a Mac OS X system with Apple's developer tools installed, then using raco ctool is typically easier than working with the C compiler directly. Use the --cgc flag to indicate that the build is for use with Racket CGC.

• Link the extension C/C++ files with "mzdyn.o" (Unix, Mac OS X) or "mzdyn.obj" (Windows) to create a shared object. The resulting shared object should use the extension ".so" (Unix), ".dll" (Windows), or ".dylib" (Mac OS X).

The "mzdyn" object file is distributed in the installation's "lib" directory. For Windows, the object file is in a compiler-specific sub-directory of "racket\lib".

The raco ctool compiler links object files into an extension when the --ld flag is specified, automatically locating "mzdyn". Again, use the --cgc flag with raco ctool.

• Load the shared object within Racket using (load-extension path), where path is the name of the extension file generated in the previous step.

Alternately, if the extension defines a module (i.e., scheme_module_name returns a symbol), then place the shared object in a special directory with a special name, so that it is detected by the module loader when require is used. The special directory is a platform-specific path that can be obtained by evaluating (build-path "compiled" "native" (system-library-subpath)); see load/use-compiled for more information. For example, if the shared object's name is "example_rkt.dll", then (require "example.rkt") will be redirected to "example_rkt.dll" if the latter is placed in the sub-directory (build-path "compiled" "native" (system-library-subpath)) and if "example.rkt" does not exist or has an earlier timestamp.

Note that (load-extension path) within a module does *not* introduce the extension's definitions into the module, because load-extension is a run-time operation. To introduce an extension's bindings into a module, make sure that the extension defines a module, put the extension in the platform-specific location as described above, and use require.

IMPORTANT: With Racket CGC, Racket values are garbage collected using a conservative garbage collector, so pointers to Racket objects can be kept in registers, stack variables, or structures allocated with scheme_malloc. However, static variables that contain pointers to collectable memory must be registered using scheme_register_extension_global (see §3 "Memory Allocation"); even then, such static variables must be thread-local (in the OS-thread sense) to work with multiple places (see §1.6 "Racket and Places").

As an example, the following C code defines an extension that returns "hello world" when it is loaded:

```
#include "escheme.h"
Scheme_Object *scheme_initialize(Scheme_Env *env) {
   return scheme_make_utf8_string("hello world");
}
Scheme_Object *scheme_reload(Scheme_Env *env) {
   return scheme_initialize(env); /* Nothing special for reload */
}
Scheme_Object *scheme_module_name() {
```

```
return scheme_false;
}
```

Assuming that this code is in the file "hw.c", the extension is compiled on Unix with the following two commands:

```
raco ctool --cgc --cc hw.c
raco ctool --cgc --ld hw.so hw.o
```

(Note that the --cgc, --cc, and --ld flags are each prefixed by two dashes, not one.)

The "collects/mzscheme/examples" directory in the Racket distribution contains additional examples.

1.4.2 3m Extensions

To build an extension to work with Racket 3m, the CGC instructions must be extended as follows:

- Adjust code to cooperate with the garbage collector as described in §3.1 "Cooperating with 3m". Using raco ctool with the --xform might convert your code to implement part of the conversion, as described in §3.1.3 "Local Pointers and raco ctool --xform".
- In either your source in the in compiler command line, #define MZ_PRECISE_GC before including "escheme.h". When using raco ctool with the --cc and --3m flags, MZ_PRECISE_GC is automatically defined.
- Link with "mzdyn3m.o" (Unix, Mac OS X) or "mzdyn3m.obj" (Windows) to create a shared object. When using raco ctool, use the --ld and --3m flags to link to these libraries.

For a relatively simple extension "hw.c", the extension is compiled on Unix for 3m with the following three commands:

```
raco ctool --xform hw.c
raco ctool --3m --cc hw.3m.c
raco ctool --3m --ld hw.so hw_3m.o
```

Some examples in "collects/mzscheme/examples" work with Racket 3m in this way. A few examples are manually instrumented, in which case the --xform step should be skipped.

1.4.3 Declaring a Module in an Extension

To create an extension that behaves as a module, return a symbol from scheme_module_name, and have scheme_initialize and scheme_rename declare a module using scheme_primitive_module.

For example, the following extension implements a module named hello that exports a binding greeting:

```
#include "escheme.h"
Scheme_Object *scheme_initialize(Scheme_Env *env) {
 Scheme_Env *mod_env;
 mod_env = scheme_primitive_module(scheme_intern_symbol("hi"),
                                    env);
  scheme_add_global("greeting",
                    scheme_make_utf8_string("hello"),
                    mod_env);
  scheme_finish_primitive_module(mod_env);
  return scheme_void;
}
Scheme_Object *scheme_reload(Scheme_Env *env) {
  return scheme_initialize(env); /* Nothing special for reload */
}
Scheme_Object *scheme_module_name() {
 return scheme_intern_symbol("hi");
}
```

This extension could be compiled for 3m on i386 Linux, for example, using the following sequence of mzc commands:

```
raco ctool --xform hi.c
raco ctool --3m --cc hi.3m.c
mkdir -p compiled/native/i386-linux/3m
raco ctool --3m --ld compiled/native/i386-linux/3m/hi_rkt.so
hi_3m.o
```

The resulting module can be loaded with

(require "hi.rkt")

1.5 Embedding Racket into a Program

Like creating extensions, the embedding process for Racket CGC or Racket 3m is essentially the same, but the process for Racket 3m is most easily understood as a variant of the process for Racket CGC.

1.5.1 CGC Embedding

To embed Racket CGC in a program, follow these steps:

• Locate or build the Racket CGC libraries. Since the standard distribution provides 3m libraries, only, you will most likely have to build from source.

On Unix, the libraries are "libracket.a" and "libmzgc.a" (or "libracket.so" and "libmzgc.so" for a dynamic-library build, with "libracket.la" and "libmzgc.la" files for use with libtool). Building from source and installing places the libraries into the installation's "lib" directory. Be sure to build the CGC variant, since the default is 3m.

On Windows, stub libraries for use with Microsoft tools are "libracketx.lib" and "libmzgcx.lib" (where x represents the version number) are in a compilerspecific directory in "racket\lib". These libraries identify the bindings that are provided by "libracketx.dll" and "libmzgcx.dll" — which are typically installed in "racket\lib". When linking with Cygwin, link to "libracketx.dll" and "libmzgcx.dll" directly. At run time, either "libracketx.dll" and "libmzgcx.dll" must be moved to a location in the standard DLL search path, or your embedding application must "delayload" link the DLLs and explicitly load them before use. ("Racket.exe" and "GRacket.exe" use the latter strategy.)

On Mac OS X, dynamic libraries are provided by the "Racket" framework, which is typically installed in "lib" sub-directory of the installation. Supply -framework Racket to gcc when linking, along with -F and a path to the "lib" directory. Beware that CGC and 3m libraries are installed as different versions within a single framework, and installation marks one version or the other as the default (by setting symbolic links); install only CGC to simplify accessing the CGC version within the framework. At run time, either "Racket.framework" must be moved to a location in the standard framework search path, or your embedding executable must provide a specific path to the framework (possibly an executable-relative path using the Mach-O @executable_path prefix).

• For each C/C++ file that uses Racket library functions, #include the file "scheme.h".

The C preprocessor symbol SCHEME_DIRECT_EMBEDDED is defined as 1 when "scheme.h" is #included, or as 0 when "escheme.h" is #included.

The "scheme.h" file is distributed with the Racket software in the installation's "include" directory. Building and installing from source also places this file in the installation's "include" directory.

• Start your main program through the scheme_main_setup (or scheme_main_stack_setup) trampoline, and put all uses of Racket functions inside the function passed to scheme_main_setup. The scheme_main_setup function registers the current C stack location with the memory manager. It also creates the initial namespace Scheme_Env* by calling scheme_basic_env and passing the result to the function provided to scheme_main_setup. (The scheme_main_stack_setup trampoline registers the C stack with the memory manager without creating a namespace.)

On 32-bit Windows, when support for parallelism is enabled in the Racket build (as is the default), then before calling scheme_main_setup, your embedding application must first call scheme_register_tls_space:

scheme_register_tls_space(&tls_space, 0);

where tls_space is declared as a thread-local pointer variable in the main executable (i.e., not in a dynamically linked DLL):

static __declspec(thread) void *tls_space;

• Configure the namespace by adding module declarations. The initial namespace contains declarations only for a few primitive modules, such as '#%kernel, and no bindings are imported into the top-level environment.

To embed a module like racket/base (along with all its dependencies), use raco ctool --c-mods, which generates a C file that contains modules in bytecode form as encapsulated in a static array. The generated C file defines a declare_modules function that takes a Scheme_Env*, installs the modules into the environment, and adjusts the module name resolver to access the embedded declarations.

Alternately, use scheme_set_collects_path and scheme_init_collection_paths to configure and install a path for finding modules at run time.

• Access Racket through scheme_dynamic_require, scheme_load, scheme_eval, and/or other functions described in this manual.

If the embedding program configures built-in parameters in a way that should be considered part of the default configuration, then call scheme_seal_parameters afterward. The snapshot of parameter values taken by scheme_seal_parameters is used for certain privileged operations, such as installing a PLaneT package.

• Compile the program and link it with the Racket libraries.

With Racket CGC, Racket values are garbage collected using a conservative garbage collector, so pointers to Racket objects can be kept in registers, stack variables, or structures

allocated with scheme_malloc. In an embedding application on some platforms, static variables are also automatically registered as roots for garbage collection (but see notes below specific to Mac OS X and Windows).

For example, the following is a simple embedding program which evaluates all expressions provided on the command line and displays the results, then runs a read-eval-print loop. Run

raco ctool --c-mods base.c ++lib racket/base

to generate "base.c", which encapsulates racket/base and all of its transitive imports (so that they need not be found separately a run time).

```
#include "scheme.h"
#include "base.c"
static int run(Scheme_Env *e, int argc, char *argv[])
ſ
 Scheme_Object *curout;
  int i;
 mz_jmp_buf * volatile save, fresh;
  /* Declare embedded modules in "base.c": */
 declare_modules(e);
  scheme_namespace_require(scheme_intern_symbol("racket/base"));
  curout = scheme_get_param(scheme_current_config(),
                            MZCONFIG_OUTPUT_PORT);
 for (i = 1; i < argc; i++) {</pre>
    save = scheme_current_thread->error_buf;
    scheme_current_thread->error_buf = &fresh;
    if (scheme_setjmp(scheme_error_buf)) {
      scheme_current_thread->error_buf = save;
      return -1; /* There was an error */
    } else {
      Scheme_Object *v, *a[2];
      v = scheme_eval_string(argv[i], e);
      scheme_display(v, curout);
      scheme_display(scheme_make_char('\n'), curout);
      /* read-eval-print loop, uses initial Scheme_Env: */
     a[0] = scheme_intern_symbol("racket/base");
      a[1] = scheme_intern_symbol("read-eval-print-loop");
      scheme_apply(scheme_dynamic_require(2, a), 0, NULL);
```

```
scheme_current_thread->error_buf = save;
}
return 0;
}
int main(int argc, char *argv[])
{
return scheme_main_setup(1, run, argc, argv);
}
```

On Mac OS X, or on Windows when Racket is compiled to a DLL using Cygwin, the garbage collector cannot find static variables automatically. In that case, scheme_main_setup must be called with a non-zero first argument.

On Windows (for any other build mode), the garbage collector finds static variables in an embedding program by examining all memory pages. This strategy fails if a program contains multiple Windows threads; a page may get unmapped by a thread while the collector is examining the page, causing the collector to crash. To avoid this problem, call scheme_main_setup with a non-zero first argument.

When an embedding application calls scheme_main_setup with a non-zero first argument, it must register each of its static variables with MZ_REGISTER_STATIC if the variable can contain a GCable pointer. For example, if curout above is made static, then MZ_REGISTER_STATIC(curout) should be inserted before the call to scheme_get_param.

When building an embedded Racket CGC to use SenoraGC (SGC) instead of the default collector, scheme_main_setup must be called with a non-zero first argument. See §3 "Memory Allocation" for more information.

1.5.2 3m Embedding

Racket 3m can be embedded mostly the same as Racket, as long as the embedding program cooperates with the precise garbage collector as described in §3.1 "Cooperating with 3m".

In either your source in the in compiler command line, #define MZ_PRECISE_GC before including "scheme.h". When using raco ctool with the --cc and --3m flags, MZ_PRECISE_GC is automatically defined.

In addition, some library details are different:

• On Unix, the library is just "libracket3m.a" (or "libracket3m.so" for a dynamic-library build, with "libracket3m.la" for use with libtool). There is no separate library for 3m analogous to CGC's "libmzgc.a".

- On Windows, the stub library for use with Microsoft tools is "libracket3mx.lib" (where x represents the version number). This library identifies the bindings that are provided by "libracket3mx.dll". There is no separate library for 3m analogous to CGC's "libmzgcx.lib".
- On Mac OS X, 3m dynamic libraries are provided by the "Racket" framework, just as for CGC, but as a version suffixed with "_3m".

For Racket 3m, an embedding application must call scheme_main_setup with a non-zero first argument.

The simple embedding program from the previous section can be processed by raco ctool --xform, then compiled and linked with Racket 3m. Alternately, the source code can be extended to work with either CGC or 3m depending on whether MZ_PRECISE_GC is defined on the compiler's command line:

```
#include "scheme.h"
#include "base.c"
static int run(Scheme_Env *e, int argc, char *argv[])
{
 Scheme_Object *curout = NULL, *v = NULL, *a[2] = {NULL, NULL};
 Scheme_Config *config = NULL;
  int i;
 mz_jmp_buf * volatile save = NULL, fresh;
 MZ_GC_DECL_REG(8);
 MZ_GC_VAR_IN_REG(0, e);
 MZ_GC_VAR_IN_REG(1, curout);
 MZ_GC_VAR_IN_REG(2, save);
 MZ_GC_VAR_IN_REG(3, config);
 MZ_GC_VAR_IN_REG(4, v);
 MZ_GC_ARRAY_VAR_IN_REG(5, a, 2);
 MZ_GC_REG();
 declare_modules(e);
  v = scheme_intern_symbol("racket/base");
  scheme_namespace_require(v);
  config = scheme_current_config();
  curout = scheme_get_param(config, MZCONFIG_OUTPUT_PORT);
 for (i = 1; i < argc; i++) {</pre>
```

```
save = scheme_current_thread->error_buf;
    scheme_current_thread->error_buf = &fresh;
    if (scheme_setjmp(scheme_error_buf)) {
      scheme_current_thread->error_buf = save;
      return -1; /* There was an error */
    } else {
      v = scheme_eval_string(argv[i], e);
      scheme_display(v, curout);
      v = scheme_make_char('\n');
      scheme_display(v, curout);
      /* read-eval-print loop, uses initial Scheme_Env: */
     a[0] = scheme_intern_symbol("racket/base");
     a[1] = scheme_intern_symbol("read-eval-print-loop");
      v = scheme_dynamic_require(2, a);
     scheme_apply(v, 0, NULL);
      scheme_current_thread->error_buf = save;
    }
 }
 MZ_GC_UNREG();
 return 0;
}
int main(int argc, char *argv[])
{
 return scheme_main_setup(1, run, argc, argv);
}
```

Strictly speaking, the config and v variables above need not be registered with the garbage collector, since their values are not needed across function calls that allocate. The code is much easier to maintain, however, when all local variables are registered and when all temporary values are put into variables.

1.6 Racket and Places

Each Racket place corresponds to a separate OS-implemented thread. Each place has its own memory manager. Pointers to GC-managed memory cannot be communicated from one place to another, because such pointers in one place are invisible to the memory manager of another place.

When place support is enabled, static variables in an extension or an embedding generally cannot hold pointers to GC-managed memory, since the static variable may be used from multiple places. For some OSes, a static variable can be made thread-local, in which case it

has a different address in each OS thread, and each different address can be registered with the GC for a given place.

The OS thread that originally calls scheme_basic_env is the OS thread of the original place. When scheme_basic_env is called a second time to reset the interpreter, it can be called in an OS thread that is different from the original call to scheme_basic_env. Thereafter, the new thread is the OS thread for the original place.

1.7 Racket and Threads

Racket implements threads for Racket programs without aid from the operating system, so that Racket threads are cooperative from the perspective of C code. On Unix, stand-alone Racket uses a single OS-implemented thread. On Windows and Mac OS X, stand-alone Racket uses a few private OS-implemented threads for background tasks, but these OS-implemented threads are never exposed by the Racket API.

In an embedding application, Racket can co-exist with additional OS-implemented threads, but the additional OS threads must not call any scheme_ function. Only the OS thread representing a particular place can call scheme_ functions. (This restriction is stronger than saying all calls for a given place must be serialized across threads. Racket relies on properties of specific threads to avoid stack overflow and garbage collection.) For the original place, only the OS thread used to call scheme_basic_env can call scheme_ functions. For any other place, only the OS thread that is created by Racket for the place can be used to call scheme_ functions.

See §8 "Threads" for more information about threads, including the possible effects of Racket's thread implementation on extension and embedding C code.

1.8 Racket, Unicode, Characters, and Strings

A character in Racket is a Unicode code point. In C, a character value has type mzchar, which is an alias for unsigned — which is, in turn, 4 bytes for a properly compiled Racket. Thus, a mzchar* string is effectively a UCS-4 string.

Only a few Racket functions use mzchar*. Instead, most functions accept char* strings. When such byte strings are to be used as a character strings, they are interpreted as UTF-8 encodings. A plain ASCII string is always acceptable in such cases, since the UTF-8 encoding of an ASCII string is itself.

See also §2.3 "Strings" and §11 "String Encodings".

1.9 Integers

Racket expects to be compiled in a mode where short is a 16-bit integer, int is a 32-bit integer, and intptr_t has the same number of bits as void*. The long type can match either int or intptr_t, depending on the platform. The mzlonglong type has 64 bits for compilers that support a 64-bit integer type, otherwise it is the same as intptr_t; thus, mzlonglong tends to match long long. The umzlonglong type is the unsigned version of mzlonglong.

2 Values and Types

A Racket value is represented by a pointer-sized value. The low bit is a mark bit: a 1 in the low bit indicates an immediate integer, a 0 indicates a (word-aligned) pointer.

A pointer Racket value references a structure that begins with a Scheme_Object substructure, which in turn starts with a tag that has the C type Scheme_Type. The rest of the structure, following the Scheme_Object header, is type-dependent. Racket's C interface gives Racket values the type Scheme_Object*. (The "object" here does not refer to objects in the sense of the racket/class library.)

Examples of Scheme_Type values include scheme_pair_type and scheme_symbol_type. Some of these are implemented as instances of Scheme_Simple_Object, which is defined in "scheme.h", but extension or embedding code should never access this structure directly. Instead, the code should use macros, such as SCHEME_CAR, that provide access to the data of common Racket types.

For most Racket types, a constructor is provided for creating values of the type. For example, scheme_make_pair takes two Scheme_Object* values and returns the cons of the values.

The macro SCHEME_TYPE takes a Scheme_Object * and returns the type of the object. This macro performs the tag-bit check, and returns scheme_integer_type when the value is an immediate integer; otherwise, SCHEME_TYPE follows the pointer to get the type tag. Macros are provided to test for common Racket types; for example, SCHEME_PAIRP returns 1 if the value is a cons cell, 0 otherwise.

In addition to providing constructors, Racket defines six global constant Racket values: scheme_true, scheme_false, scheme_null, scheme_eof, scheme_void, and scheme_undefined. Each of these has a type tag, but each is normally recognized via its constant address.

An extension or embedding application can create new a primitive data type by calling scheme_make_type, which returns a fresh Scheme_Type value. To create a collectable instance of this type, allocate memory for the instance with scheme_malloc_atomic. From Racket's perspective, the main constraint on the data format of such an instance is that the first sizeof(Scheme_Object) bytes must correspond to a Scheme_Object record; furthermore, the first sizeof(Scheme_Type) bytes must contain the value returned by scheme_make_type. Extensions with modest needs can use scheme_make_cptr, instead of creating an entirely new type.

Racket values should never be allocated on the stack, and they should never contain pointers to values on the stack. Besides the problem of restricting the value's lifetime to that of the stack frame, allocating values on the stack creates problems for continuations and threads, both of which copy into and out of the stack.

2.1 Standard Types

The following are the Scheme_Type values for the standard types:

- scheme_bool_type the constants scheme_true and scheme_false are the only values of this type; use SCHEME_FALSEP to recognize scheme_false and use SCHEME_TRUEP to recognize anything except scheme_false; test for this type with SCHEME_BOOLP
- scheme_char_type SCHEME_CHAR_VAL extracts the character (of type mzchar); test for this type with SCHEME_CHARP
- scheme_integer_type fixnum integers, which are identified via the tag bit rather than following a pointer to this Scheme_Type value; SCHEME_INT_VAL extracts the integer to an intptr_t; test for this type with SCHEME_INTP
- scheme_double_type flonum inexact numbers; SCHEME_FLOAT_VAL or SCHEME_DBL_VAL extracts the floating-point value; test for this type with SCHEME_DBLP
- scheme_float_type single-precision flonum inexact numbers, when specifically enabled when compiling Racket; SCHEME_FLOAT_VAL or SCHEME_FLT_VAL extracts the floating-point value; test for this type with SCHEME_FLTP
- scheme_bignum_type test for this type with SCHEME_BIGNUMP
- scheme_rational_type test for this type with SCHEME_RATIONALP
- scheme_complex_type test for this type or scheme_complex_izi_type with
 SCHEME_COMPLEXP
- scheme_complex_izi_type complex number with an inexact zero imaginary part (so it counts as a real number); test for this type specifically with SCHEME_COMPLEX_IZIP
- scheme_char_string_type SCHEME_CHAR_STR_VAL extracts the string as a mzchar*; the string is always nul-terminated, but may also contain embedded nul characters, and the Racket string is modified if this string is modified; SCHEME_CHAR_STRLEN_VAL extracts the string length (in characters, not counting the nul terminator); test for this type with SCHEME_CHAR_STRINGP
- scheme_byte_string_type SCHEME_BYTE_STR_VAL extracts the string as a char*; the string is always nul-terminated, but may also contain embedded nul characters, and the Racket string is modified if this string is modified; SCHEME_BYTE_STRLEN_VAL extracts the string length (in bytes, not counting the nul terminator); test for this type with SCHEME_BYTE_STRINGP
- scheme_path_type SCHEME_PATH_VAL extracts the path as a char*; the string is always nul-terminated; SCHEME_PATH_LEN extracts the path length (in bytes, not counting the nul terminator); test for this type with SCHEME_PATHP

- scheme_symbol_type SCHEME_SYM_VAL extracts the symbol's string as a char* UTF-8 encoding (do not modify this string); SCHEME_SYM_LEN extracts the number of bytes in the symbol name (not counting the nul terminator); test for this type with SCHEME_SYMBOLP; 3m: see §3.1 "Cooperating with 3m" for a caution about SCHEME_SYM_VAL
- scheme_keyword_type SCHEME_KEYWORD_VAL extracts the keyword's string (without the leading hash colon) as a char* UTF-8 encoding (do not modify this string); SCHEME_KEYWORD_LEN extracts the number of bytes in the keyword name (not counting the nul terminator); test for this type with SCHEME_KEYWORDP; 3m: see §3.1 "Cooperating with 3m" for a caution about SCHEME_KEYWORD_VAL
- scheme_box_type SCHEME_BOX_VAL extracts/sets the boxed value; test for this type with SCHEME_BOXP
- scheme_pair_type SCHEME_CAR extracts/sets the car and SCHEME_CDR extracts/sets the cdr; test for this type with SCHEME_PAIRP
- scheme_mutable_pair_type SCHEME_MCAR extracts/sets the mcar and SCHEME_MCDR extracts/sets the mcdr; test for this type with SCHEME_MPAIRP
- scheme_vector_type SCHEME_VEC_SIZE extracts the length and SCHEME_VEC_ELS extracts the array of Racket values (the Racket vector is modified when this array is modified); test for this type with SCHEME_VECTORP; 3m: see §3.1 "Cooperating with 3m" for a caution about SCHEME_VEC_ELS
- scheme_flvector_type SCHEME_FLVEC_SIZE extracts the length and SCHEME_FLVEC_ELS extracts the array of doubles; test for this type with SCHEME_FLVECTORP; 3m: see §3.1 "Cooperating with 3m" for a caution about SCHEME_FLVEC_ELS
- scheme_fxvector_type uses the same representation as scheme_vector_type, so use SCHEME_VEC_SIZE for the length and SCHEME_VEC_ELS for the array of Racket fixnum values; test for this type with SCHEME_FXVECTORP; 3m: see §3.1 "Cooperating with 3m" for a caution about SCHEME_VEC_ELS
- scheme_structure_type structure instances; test for this type with SCHEME_STRUCTP
- scheme_struct_type_type structure types; test for this type with SCHEME_STRUCT_TYPEP
- scheme_struct_property_type structure type properties
- scheme_input_port_type SCHEME_INPORT_VAL extracts/sets the user data pointer; test for just this type with SCHEME_INPORTP, but use SCHEME_INPUT_PORTP to recognize all input ports (including structures with the prop:input-port property)

- scheme_output_port_type SCHEME_OUTPORT_VAL extracts/sets the user data pointer; test for just this type with SCHEME_OUTPORTP, but use SCHEME_OUTPUT_PORTP to recognize all output ports (including structures with the prop:output-port property)
- scheme_thread_type thread descriptors; test for this type with SCHEME_THREADP
- scheme_sema_type semaphores; test for this type with SCHEME_SEMAP
- scheme_hash_table_type test for this type with SCHEME_HASHTP
- scheme_bucket_table_type test for this type with SCHEME_BUCKTP
- scheme_weak_box_type test for this type with SCHEME_WEAKP; SCHEME_WEAK_PTR extracts the contained object, or NULL after the content is collected; do not set the content of a weak box
- scheme_namespace_type namespaces; test for this type with SCHEME_NAMESPACEP
- scheme_cpointer_type #<void> pointer with a type-describing Scheme_Object; SCHEME_CPTR_VAL extracts the pointer and SCHEME_CPTR_TYPE extracts the type tag object; test for this type with SCHEME_CPTRP. The tag is used when printing such objects when it's a symbol, a byte string, a string, or a pair holding one of these in its car.

The following are the procedure types:

- scheme_prim_type a primitive procedure, possibly with data elements
- scheme_closed_prim_type an old-style primitive procedure with a data pointer
- scheme_compiled_closure_type a Racket procedure
- scheme_cont_type a continuation
- scheme_escaping_cont_type an escape continuation
- scheme_case_closure_type a case-lambda procedure
- scheme_native_closure_type a procedure with native code generated by the
 just-in-time compiler

The predicate SCHEME_PROCP returns 1 for all procedure types and 0 for anything else.

The following are additional number predicates:

• SCHEME_NUMBERP — all numerical types

- SCHEME_REALP all non-complex numerical types, plus scheme_complex_izi_type
- SCHEME_EXACT_INTEGERP fixnums and bignums
- SCHEME_EXACT_REALP fixnums, bignums, and rationals
- SCHEME_FLOATP both single-precision (when enabled) and double-precision flonums

2.2 Global Constants

There are six global constants:

- scheme_null test for this value with SCHEME_NULLP
- scheme_eof test for this value with SCHEME_EOFP
- scheme_true
- scheme_false test for this value with SCHEME_FALSEP; test *against* it with SCHEME_TRUEP
- scheme_void test for this value with SCHEME_VOIDP
- scheme_undefined

2.3 Strings

As noted in §1.8 "Racket, Unicode, Characters, and Strings", a Racket character is a Unicode code point represented by a mzchar value, and character strings are mzchar arrays. Racket also supplies byte strings, which are char arrays.

For a character string *s*, SCHEME_CHAR_STR_VAL(*s*) produces a pointer to mzchars, not chars. Convert a character string to its UTF-8 encoding as byte string with scheme_char_string_to_byte_string. For a byte string *bs*, SCHEME_BYTE_STR_VAL(*bs*) produces a pointer to chars. The function scheme_byte_string_to_char_string decodes a byte string as UTF-8 and produces a character string. The functions scheme_char_string_to_byte_string_locale and scheme_byte_string_to_char_string_locale are similar, but they use the current locale's encoding instead of UTF-8.

For more fine-grained control over UTF-8 encoding, use the scheme_utf8_decode and scheme_utf8_encode functions, which are described in §11 "String Encodings".

2.4 Value Functions

Scheme_Object* scheme_make_char(mzchar *ch*)

Returns the character value. The *ch* value must be a legal Unicode code point (and not a surrogate, for example). The first 256 characters are represented by constant Racket values, and others are allocated.

Scheme_Object* scheme_make_char_or_null(mzchar *ch*)

Like scheme_make_char, but the result is NULL if ch is not a legal Unicode code point.

Scheme_Object* scheme_make_character(mzchar *ch*)

Returns the character value. This is a macro that directly accesses the array of constant characters when ch is less than 256.

Scheme_Object* scheme_make_ascii_character(mzchar *ch*)

Returns the character value, assuming that *ch* is less than 256. (This is a macro.)

```
Scheme_Object* scheme_make_integer(intptr_t i)
```

Returns the integer value; *i* must fit in a fixnum. (This is a macro.)

```
Scheme_Object* scheme_make_integer_value(intptr_t i)
```

Returns the integer value. If *i* does not fit in a fixnum, a bignum is returned.

```
Scheme_Object*
scheme_make_integer_value_from_unsigned(uintptr_t i)
```

Like scheme_make_integer_value, but for unsigned integers.

```
Scheme_Object*
scheme_make_integer_value_from_long_long(mzlonglong i)
```

Like scheme_make_integer_value, but for mzlonglong values (see §1.9 "Integers").

```
Scheme_Object*
scheme_make_integer_value_from_unsigned_long_long(umzlonglong i)
```

Like scheme_make_integer_value_from_long_long, but for unsigned integers.

Creates an integer given the high and low intptr_ts of a signed integer. Note that on 64bit platforms where long long is the same as intptr_t, the resulting integer has 128 bits.

```
(See also §1.9 "Integers".)
```

```
Scheme_Object*
scheme_make_integer_value_from_unsigned_long_halves(uintptr_t hi,
uintptr_t lo)
```

Creates an integer given the high and low intptr_ts of an unsigned integer. Note that on 64-bit platforms where long long is the same as intptr_t, the resulting integer has 128 bits.

Extracts the integer value. Unlike the SCHEME_INT_VAL macro, this procedure will extract an integer that fits in a intptr_t from a Racket bignum. If *o* fits in a intptr_t, the extracted integer is placed in **i* and 1 is returned; otherwise, 0 is returned and **i* is unmodified.

Like scheme_get_int_val, but for unsigned integers.

Like scheme_get_int_val, but for mzlonglong values (see §1.9 "Integers").

Like scheme_get_int_val, but for unsigned mzlonglong values (see §1.9 "Integers").

```
Scheme_Object* scheme_make_double(double d)
```

Creates a new floating-point value.

```
Scheme_Object* scheme_make_float(float d)
```

Creates a new single-precision floating-point value. The procedure is available only when Racket is compiled with single-precision numbers enabled.

```
double scheme_real_to_double(Scheme_Object* o)
```

Converts a Racket real number to a double-precision floating-point value.

Makes a cons pair.

Scheme_Object* scheme_make_byte_string(char* bytes)

Makes a Racket byte string from a nul-terminated C string. The bytes string is copied.

```
Scheme_Object*
scheme_make_byte_string_without_copying(char* bytes)
```

Like scheme_make_byte_string, but the string is not copied.

Makes a byte string value with size *len*. A copy of *bytes* is made if *copy* is not 0. The string *bytes* should contain *len* bytes; *bytes* can contain the nul byte at any position, and need not be nul-terminated if *copy* is non-zero. However, if *len* is negative, then the nul-terminated length of *bytes* is used for the length, and if *copy* is zero, then *bytes* must be nul-terminated.

Like scheme_make_sized_byte_string, except the *len* characters start from position *d* in *bytes*. If *d* is non-zero, then *copy* must be non-zero.

Allocates a new Racket byte string.

Creates a new byte string by appending the two given byte strings.

```
Scheme_Object* scheme_make_locale_string(char* bytes)
```

Makes a Racket string from a nul-terminated byte string that is a locale-specific encoding of a character string; a new string is allocated during decoding. The "locale in the name of this function thus refers to *bytes*, and not the resulting string (which is internally stored as UCS-4).

```
Scheme_Object* scheme_make_utf8_string(char* bytes)
```

Makes a Racket string from a nul-terminated byte string that is a UTF-8 encoding. A new string is allocated during decoding. The "utf8" in the name of this function thus refers to *bytes*, and not the resulting string (which is internally stored as UCS-4).

Makes a string value, based on *len* UTF-8-encoding bytes (so the resulting string is *len* characters or less). The string *bytes* should contain at least *len* bytes; *bytes* can contain the nul byte at any position, and need not be null-terminated. However, if *len* is negative, then the nul-terminated length of *bytes* is used for the length.

Like scheme_make_sized_char_string, except the *len* characters start from position *d* in *bytes*.

Scheme_Object* scheme_make_char_string(mzchar* *chars*)

Makes a Racket string from a nul-terminated UCS-4 string. The chars string is copied.

```
Scheme_Object*
scheme_make_char_string_without_copying(mzchar* chars)
```

Like scheme_make_char_string, but the string is not copied.

Makes a string value with size *len*. A copy of *chars* is made if *copy* is not 0. The string *chars* should contain *len* characters; *chars* can contain the nul character at any position, and need not be nul-terminated if *copy* is non-zero. However, if *len* is negative, then the nul-terminated length of *chars* is used for the length, and if *copy* is zero, then the *chars* must be nul-terminated.

Like scheme_make_sized_char_string, except the *len* characters start from position *d* in *chars*. If *d* is non-zero, then *copy* must be non-zero.

Scheme_Object* scheme_alloc_char_string(intptr_t size, mzchar fill)

Allocates a new Racket string.

```
Scheme_Object* scheme_append_char_string(Scheme_Object* a,
Scheme_Object* b)
```

Creates a new string by appending the two given strings.

```
Scheme_Object*
scheme_char_string_to_byte_string(Scheme_Object* s)
```

Converts a Racket character string into a Racket byte string via UTF-8.

```
Scheme_Object*
scheme_byte_string_to_char_string(Scheme_Object* s)
```

Converts a Racket byte string into a Racket character string via UTF-8.

```
Scheme_Object*
scheme_char_string_to_byte_string_locale(Scheme_Object* s)
```

Converts a Racket character string into a Racket byte string via the locale's encoding.

```
Scheme_Object*
scheme_byte_string_to_char_string_locale(Scheme_Object* s)
```

Converts a Racket byte string into a Racket character string via the locale's encoding.

```
Scheme_Object* scheme_intern_symbol(char* name)
```

Finds (or creates) the symbol matching the given nul-terminated, ASCII string (not UTF-8). The case of *name* is (non-destructively) normalized before interning if scheme_case_sensitive is 0.

Creates or finds a symbol given the symbol's length in UTF-8-encoding bytes. The case of *name* is not normalized.

Like scheme_intern_exact_symbol, but given a character array instead of a UTF-8encoding byte array.

Scheme_Object* scheme_make_symbol(char* *name*)

Creates an uninterned symbol from a nul-terminated, UTF-8-encoding string. The case is not normalized.

Creates an uninterned symbol given the symbol's length in UTF-8-encoded bytes.

Creates or finds a keyword given the keywords length in UTF-8-encoding bytes. The case of *name* is not normalized, and it should not include the leading hash and colon of the keyword's printed form.

Like scheme_intern_exact_keyword, but given a character array instead of a UTF-8encoding byte array.

Allocates a new vector.

Scheme_Double_Vector* scheme_alloc_flvector(intptr_t size)

Allocates an uninitialized flvector. The result type is effectively an alias for Scheme_Object*.

Scheme_Vector* scheme_alloc_fxvector(intptr_t size)

Allocates an uninitialized fxvector. The result type is effectively an alias for Scheme_Object*.

Scheme_Object* scheme_box(Scheme_Object* v)

Creates a new box containing the value *v*.

Scheme_Object* scheme_make_weak_box(Scheme_Object* v)

Creates a new weak box containing the value *v*.

Scheme_Type scheme_make_type(char* *name*)

Creates a new type (not a Racket value). The type tag is valid across all places.

Creates a C-pointer object that encapsulates *ptr* and uses *typetag* to identify the type of the pointer. The SCHEME_CPTRP macro recognizes objects created by scheme_make_cptr. The SCHEME_CPTR_VAL macro extracts the original *ptr* from the Racket object, and SCHEME_CPTR_TYPE extracts the type tag. The SCHEME_CPTR_OFFSETVAL macro returns 0 for the result Racket object.

The *ptr* can refer to either memory managed by the garbage collector or by some other memory manager. Beware, however, of retaining a *ptr* that refers to memory released by another memory manager, since the enclosing memory range might later become managed by the garbage collector (in which case *ptr* might become an invalid pointer that can crash the garbage collector).

Like scheme_make_cptr, but *ptr* is never treated as referencing memory managed by the garbage collector.

Creates a C-pointer object that encapsulates both *ptr* and *offset*. The SCHEME_CPTR_OFFSETVAL macro returns *offset* for the result Racket object (and the macro be used to change the offset, since it also works on objects with no offset).

The *ptr* can refer to either memory managed by the garbage collector or by some other memory manager; see also scheme_make_cptr.

Like scheme_make_offset_cptr, but *ptr* is never treated as referencing memory managed by the garbage collector.

Installs a printer to be used for printing (or writing or displaying) values that have the type tag *type*.

The type of *printer* is defined as follows:

Such a printer must print a representation of the value using scheme_print_bytes and scheme_print_string. The first argument to the printer, v, is the value to be printed. The second argument indicates whether v is printed via write or display. The last argument is to be passed on to scheme_print_bytes or scheme_print_string to identify

the printing context.

Writes the content of *str* — starting from *offset* and running *len* bytes — into a printing context determined by *pp*. This function is for use by a printer that is installed with scheme_set_type_printer.

Writes the content of *str* — starting from *offset* and running *len* characters — into a printing context determined by *pp*. This function is for use by a printer that is installed with scheme_set_type_printer.

Installs an equality predicate and associated hash functions for values that have the type tag *type*. The *equalp* predicate is only applied to values that both have tag *type*.

The type of equalp, hash1, and hash2 are defined as follows:

The two hash functions are use to generate primary and secondary keys for double hashing in an equal?-based hash table. The result of the primary-key function should depend on both *obj* and *base*.

The *cycle_data* argument in each case allows checking and hashing on cyclic values. It is intended for use in recursive checking or hashing via scheme_recur_equal, scheme_recur_equal_hash_key, and scheme_recur_equal_hash_key. That is, do not call plain scheme_equal, scheme_equal_hash_key, or scheme_equal_hash_key for recursive checking or hashing on sub-elements of the given value(s).

3 Memory Allocation

Racket uses both malloc and allocation functions provided by a garbage collector. Embedding/extension C/C++ code may use either allocation method, keeping in mind that pointers to garbage-collectable blocks in malloced memory are invisible (i.e., such pointers will not prevent the block from being garbage-collected).

Racket CGC uses a conservative garbage collector. This garbage collector normally only recognizes pointers to the beginning of allocated objects. Thus, a pointer into the middle of a GC-allocated string will normally not keep the string from being collected. The exception to this rule is that pointers saved on the stack or in registers may point to the middle of a collectable object. Thus, it is safe to loop over an array by incrementing a local pointer variable.

Racket 3m uses a precise garbage collector that moves objects during collection, in which case the C code must be instrumented to expose local pointer bindings to the collector, and to provide tracing procedures for (tagged) records containing pointers. This instrumentation is described further in §3.1 "Cooperating with 3m".

The basic collector allocation functions are:

- scheme_malloc Allocates collectable memory that may contain pointers to collectable objects; for 3m, the memory must be an array of pointers (though not necessarily to collectable objects). The newly allocated memory is initially zeroed.
- scheme_malloc_atomic Allocates collectable memory that does not contain pointers to collectable objects. If the memory does contain pointers, they are invisible to the collector and will not prevent an object from being collected. Newly allocated atomic memory is not necessary zeroed.

Atomic memory is used for strings or other blocks of memory which do not contain pointers. Atomic memory can also be used to store intentionally-hidden pointers.

- scheme_malloc_tagged Allocates collectable memory that contains a mixture of
 pointers and atomic data. With the conservative collector, this function is the same
 as scheme_malloc, but on 3m, the type tag stored at the start of the block is used to
 determine the size and shape of the object for future garbage collection (as described
 in §3.1 "Cooperating with 3m").
- scheme_malloc_allow_interior Allocates an array of pointers such that the array is never moved by the garbage collector and references are allowed into the middle of the block on 3m (and pointers to the middle prevent the block from being collected). Use this procedure sparingly, because small, non-moving objects are handled less efficiently than movable objects by the 3m collector. This procedure is the same as scheme_malloc with the conservative collector, but in the that case, having only a pointer into the interior will not prevent the array from being collected.

- scheme_malloc_atomic_allow_interior Like scheme_malloc_allow_interior for memory that does not contain pointers.
- scheme_malloc_uncollectable Allocates uncollectable memory that may contain pointers to collectable objects. There is no way to free the memory. The newly allocated memory is initially zeroed. This function is not available in 3m.

If a Racket extension stores Racket pointers in a global or static variable, then that variable must be registered with scheme_register_extension_global; this makes the pointer visible to the garbage collector. Registered variables need not contain a collectable pointer at all times (even with 3m, but the variable must contain some pointer, possibly uncollectable, at all times). Beware that static or global variables that are not thread-specific (in the OS sense of "thread") generally do not work with multiple places.

Registration is needed for the global and static variables of an embedding program on most platforms, and registration is needed on all platforms if the program calls scheme_main_setup or scheme_set_stack_base with a non-zero first or second (respectively) argument. Global and static variables containing collectable pointers must be registered with scheme_register_static. The MZ_REGISTER_STATIC macro takes any variable name and registers it with scheme_register_static. The scheme_register_static function can be safely called even when it's not needed, but it must not be called multiple times for a single memory address. When using scheme_set_stack_base and when places are enabled, then scheme_register_static or MZ_REGISTER_STATIC normally should be used only after scheme_basic_env, since scheme_basic_env changes the allocation space as explained in §3.1.5 "Places and Garbage Collector Instances".

Collectable memory can be temporarily locked from collection by using the referencecounting function scheme_dont_gc_ptr. On 3m, such locking does not prevent the object from being moved.

Garbage collection can occur during any call into Racket or its allocator, on anytime that Racket has control, except during functions that are documented otherwise. The predicate and accessor macros listed in §2.1 "Standard Types" never trigger a collection.

3.1 Cooperating with 3m

To allow 3m's precise collector to detect and update pointers during garbage collection, all pointer values must be registered with the collector, at least during the times that a collection may occur. The content of a word registered as a pointer must contain either NULL, a pointer to the start of a collectable object, a pointer into an object allocated by scheme_malloc_allow_interior, a pointer to an object currently allocated by another memory manager (and therefore not into a block that is currently managed by the collector), or a pointer to an odd-numbered address (e.g., a Racket fixnum). Pointers are registered in three different ways:

- Pointers in static variables should be registered with scheme_register_static or MZ_REGISTER_STATIC.
- Pointers in allocated memory are registered automatically when they are in an array allocated with scheme_malloc, etc. When a pointer resides in an object allocated with scheme_malloc_tagged, etc.~the tag at the start of the object identifiers the object's size and shape. Handling of tags is described in §3.1.1 "Tagged Objects".
- Local pointers (i.e., pointers on the stack or in registers) must be registered through the MZ_GC_DECL_REG, etc. macros that are described in §3.1.2 "Local Pointers".

A pointer must never refer to the interior of an allocated object (when a garbage collection is possible), unless the object was allocated with scheme_malloc_allow_interior. For this reason, pointer arithmetic must usually be avoided, unless the variable holding the generated pointer is NULLed before a collection.

IMPORTANT: The SCHEME_SYM_VAL, SCHEME_KEYWORD_VAL, SCHEME_VEC_ELS, and SCHEME_PRIM_CLOSURE_ELS macros produce pointers into the middle of their respective objects, so the results of these macros must not be held during the time that a collection can occur. Incorrectly retaining such a pointer can lead to a crash.

3.1.1 Tagged Objects

As explained in §2 "Values and Types", the scheme_make_type function can be used to obtain a new tag for a new type of object. These new types are in relatively short supply for 3m; the maximum tag is 512, and Racket itself uses nearly 300.

After allocating a new tag in 3m (and before creating instances of the tag), a *size procedure*, a *mark procedure*, and a *fixup procedure* must be installed for the tag using GC_register_traversers. A type tag and its associated GC procedures apply to all places, even though specific allocated objects are confined to a particular place.

A size procedure simply takes a pointer to an object with the tag and returns its size in words (not bytes). The gcBYTES_TO_WORDS macro converts a byte count to a word count.

A mark procedure is used to trace references among objects without moving any objects. The procedure takes a pointer to an object, and it should apply the gcMARK macro to every pointer within the object. The mark procedure should return the same result as the size procedure.

A fixup procedure is used to update references to objects after or while they are moved. The procedure takes a pointer to an object, and it should apply the gcFIXUP macro to every pointer within the object; the expansion of this macro takes the address of its argument. The fixup procedure should return the same result as the size procedure.

Depending on the collector's implementation, the mark or fixup procedure might not be used. For example, the collector may only use the mark procedure and not actually move the object. Or it may use the fixup procedure to mark and move objects at the same time. To dereference an object pointer during a fixup procedure, use GC_fixup_self to convert the address passed to the procedure to refer to the potentially moved object, and use GC_resolve to convert an address that is not yet fixed up to determine the object's current location.

When allocating a tagged object in 3m, the tag must be installed immediately after the object is allocated—or, at least, before the next possible collection.

3.1.2 Local Pointers

The 3m collector needs to know the address of every local or temporary pointer within a function call at any point when a collection can be triggered. Beware that nested function calls can hide temporary pointers; for example, in

the result from one scheme_make_pair call is on the stack or in a register during the other call to scheme_make_pair; this pointer must be exposed to the garbage collection and made subject to update. Simply changing the code to

does not expose all pointers, since tmp must be evaluated before the second call to scheme_make_pair. In general, the above code must be converted to the form

```
tmp1 = scheme_make_pair(scheme_true, scheme_false);
tmp2 = scheme_make_pair(scheme_true, scheme_false);
scheme_make_pair(tmp1, tmp2);
```

and this is converted form must be instrumented to register tmp1 and tmp2. The final result might be

```
{
   Scheme_Object *tmp1 = NULL, *tmp2 = NULL, *result;
   MZ_GC_DECL_REG(2);
   MZ_GC_VAR_IN_REG(0, tmp1);
```

```
MZ_GC_VAR_IN_REG(1, tmp2);
MZ_GC_REG();
tmp1 = scheme_make_pair(scheme_true, scheme_false);
tmp2 = scheme_make_pair(scheme_true, scheme_false);
result = scheme_make_pair(tmp1, tmp2);
MZ_GC_UNREG();
return result;
}
```

Notice that result is not registered above. The MZ_GC_UNREG macro cannot trigger a garbage collection, so the result variable is never live during a potential collection. Note also that tmp1 and tmp2 are initialized with NULL, so that they always contain a pointer whenever a collection is possible.

The MZ_GC_DECL_REG macro expands to a local-variable declaration to hold information for the garbage collector. The argument is the number of slots to provide for registration. Registering a simple pointer requires a single slot, whereas registering an array of pointers requires three slots. For example, to register a pointer tmp and an array of 10 char*s:

```
{
  Scheme_Object *tmp1 = NULL;
  char *a[10];
  int i;
  MZ_GC_DECL_REG(4);
  MZ_GC_DECL_REG(4);
  MZ_GC_VAR_IN_REG(3, tmp1);
  /* Clear a before a potential GC: */
  for (i = 0; i < 10; i++) a[i] = NULL;
   ...
  f(a);
  ...
}</pre>
```

The MZ_GC_ARRAY_VAR_IN_REG macro registers a local array given a starting slot, the array variable, and an array size. The MZ_GC_VAR_IN_REG macro takes a slot and simple pointer variable. A local variable or array must not be registered multiple times.

In the above example, the first argument to MZ_GC_VAR_IN_REG is 3 because the information for a uses the first three slots. Even if a is not used after the call to f, a must be registered with the collector during the entire call to f, because f presumably uses a until it returns.

The name used for a variable need not be immediate. Structure members can be supplied as well:

```
{
    struct { void *s; int v; void *t; } x = {NULL, 0, NULL};
    MZ_GC_DECL_REG(2);
    MZ_GC_VAR_IN_REG(0, x.s);
    MZ_GC_VAR_IN_REG(0, x.t);
    ...
}
```

In general, the only constraint on the second argument to MZ_GC_VAR_IN_REG or MZ_GC_ARRAY_VAR_IN_REG is that & must produce the relevant address, and that address must be on the stack.

Pointer information is not actually registered with the collector until the MZ_GC_REG macro is used. The MZ_GC_UNREG macro de-registers the information. Each call to MZ_GC_REG must be balanced by one call to MZ_GC_UNREG.

Pointer information need not be initialized with MZ_GC_VAR_IN_REG and MZ_GC_ARRAY_VAR_IN_REG before calling MZ_GC_REG, and the set of registered pointers can change at any time—as long as all relevant pointers are registered when a collection might occur. The following example recycles slots and completely de-registers information when no pointers are relevant. The example also illustrates how MZ_GC_UNREG is not needed when control escapes from the function, such as when scheme_signal_error escapes.

```
{
   Scheme_Object *tmp1 = NULL, *tmp2 = NULL;
   mzchar *a, *b;
   MZ_GC_DECL_REG(2);
   MZ_GC_VAR_IN_REG(0, tmp1);
   MZ_GC_VAR_IN_REG(1, tmp2);
   tmp1 = scheme_make_utf8_string("foo");
   MZ_GC_REG();
   tmp2 = scheme_make_utf8_string("bar");
   tmp1 = scheme_append_char_string(tmp1, tmp2);
   if (SCHEME_FALSEP(tmp1))
      scheme_signal_error("shouldn't happen!");
   a = SCHEME_CHAR_VAL(tmp1);
   MZ_GC_VAR_IN_REG(0, a);
   tmp2 = scheme_make_pair(scheme_read_bignum(a, 0, 10), tmp2);
   }
}
```

```
MZ_GC_UNREG();
if (SCHEME_INTP(tmp2)) {
  return 0;
}
MZ_GC_REG();
tmp1 = scheme_make_pair(scheme_read_bignum(a, 0, 8), tmp2);
MZ_GC_UNREG();
return tmp1;
}
```

A MZ_GC_DECL_REG can be used in a nested block to hold declarations for the block's variables. In that case, the nested MZ_GC_DECL_REG must have its own MZ_GC_REG and MZ_GC_UNREG calls.

```
{
 Scheme_Object *accum = NULL;
 MZ_GC_DECL_REG(1);
 MZ_GC_VAR_IN_REG(0, accum);
 MZ_GC_REG();
 accum = scheme_make_pair(scheme_true, scheme_null);
  ſ
   Scheme_Object *tmp = NULL;
   MZ_GC_DECL_REG(1);
   MZ_GC_VAR_IN_REG(0, tmp);
    MZ_GC_REG();
    tmp = scheme_make_pair(scheme_true, scheme_false);
   accum = scheme_make_pair(tmp, accum);
    MZ_GC_UNREG();
 }
 accum = scheme_make_pair(scheme_true, accum);
 MZ_GC_UNREG();
 return accum;
}
```

Variables declared in a local block can also be registered together with variables from an enclosing block, but the local-block variable must be unregistered before it goes out of scope. The MZ_GC_NO_VAR_IN_REG macro can be used to unregister a variable or to initialize a slot as having no variable.

```
{
 Scheme_Object *accum = NULL;
 MZ GC DECL REG(2);
 MZ_GC_VAR_IN_REG(0, accum);
 MZ_GC_NO_VAR_IN_REG(1);
 MZ_GC_REG();
  accum = scheme_make_pair(scheme_true, scheme_null);
  {
    Scheme_Object *tmp = NULL;
    MZ_GC_VAR_IN_REG(1, tmp);
   tmp = scheme_make_pair(scheme_true, scheme_false);
    accum = scheme_make_pair(tmp, accum);
    MZ_GC_NO_VAR_IN_REG(1);
 }
  accum = scheme_make_pair(scheme_true, accum);
 MZ_GC_UNREG();
 return accum;
}
```

The MZ_GC_ macros all expand to nothing when MZ_PRECISE_GC is not defined, so the macros can be placed into code to be compiled for both conservative and precise collection.

The MZ_GC_REG and MZ_GC_UNREG macros must never be used in an OS thread other than Racket's thread.

3.1.3 Local Pointers and raco ctool --xform

When raco ctool is run with the --xform flag and a source C program, it produces a C program that is instrumented in the way described in the previous section (but with a slightly different set of macros). For each input file "name.c", the transformed output is "name.3m.c".

The --xform mode for raco ctool does not change allocation calls, nor does it generate size, mark, or fixup procedures. It merely converts the code to register local pointers.

Furthermore, the --xform mode for raco ctool does not handle all of C. It's ability to rearrange compound expressions is particularly limited, because --xform merely converts expression text heuristically instead of parsing C. A future version of the tool will correct such problems. For now, raco ctool in --xform mode attempts to provide reasonable error messages when it is unable to convert a program, but beware that it can miss cases. To an even more limited degree, --xform can work on C++ code. Inspect the output of

--xform mode to ensure that your code is correctly instrumented.

Some specific limitations:

- The body of a for, while, or do loop must be surrounded with curly braces. (A conversion error is normally reported, otherwise.)
- Function calls may not appear on the right-hand side of an assignment within a declaration block. (A conversion error is normally reported if such an assignment is discovered.)
- Multiple function calls in ... ? ... : ... cannot be lifted. (A conversion error is normally reported, otherwise.)
- In an assignment, the left-hand side must be a local or static variable, not a field selection, pointer dereference, etc. (A conversion error is normally reported, otherwise.)
- The conversion assumes that all function calls use an immediate name for a function, as opposed to a compound expression as in s->f(). The function name need not be a top-level function name, but it must be bound either as an argument or local variable with the form *type id*; the syntax *ret_type* (**id*)(...) is not recognized, so bind the function type to a simple name with typedef, first: typedef *ret_type* (**type*)(...); *type id*.
- Arrays and structs must be passed by address, only.
- GC-triggering code must not appear in system headers.
- Pointer-comparison expressions are not handled correctly when either of the compared expressions includes a function call. For example, a() == b() is not converted correctly when a and b produce pointer values.
- Passing the address of a local pointer to a function works only when the pointer variable remains live after the function call.
- A return; form can get converted to { *stmt*; return; };, which can break an if (...) return; else ... pattern.
- Local instances of union types are generally not supported.
- · Pointer arithmetic cannot be converted away, and is instead reported as an error.

3.1.4 Guiding raco ctool --xform

The following macros can be used (with care!) to navigate --xform around code that it cannot handle:

• XFORM_START_SKIP and XFORM_END_SKIP: code between these two statements is ignored by the transform tool, except to tokenize it.

Example:

```
int foo(int c, ...) {
    int r = 0;
    XFORM_START_SKIP;
    {
        /* va plays strange tricks that confuse xform */
        va_list args;
        va_start(args, c);
        while (c--) {
            r += va_arg(args, int);
        }
    }
    XFORM_END_SKIP;
    return r;
}
```

These macros can also be used at the top level, outside of any function. Since they have to be terminated by a semi-colon, however, top-level uses usually must be wrapped with #ifdef MZ_PRECISE_GC and #endif; a semi-colon by itself at the top level is not legal in C.

• XFORM_SKIP_PROC: annotate a function so that its body is skipped in the same way as bracketing it with XFORM_START_SKIP and XFORM_END_SKIP.

Example:

```
int foo(int c, ...) XFORM_END_SKIP {
}
```

• XFORM_HIDE_EXPR: a macro that takes wraps an expression to disable processing of the expression.

Example:

```
int foo(int c, ...) {
    int r = 0;
    {
        /* va plays strange tricks that confuse xform */
        XFORM_CAN_IGNORE va_list args; /* See below */
        XFORM_HIDE_EXPR(va_start(args, c));
        while (c--) {
            r += XFORM_HIDE_EXPR(va_arg(args, int));
        }
    }
    return r;
}
```

- XFORM_CAN_IGNORE: a macro that acts like a type modifier (must appear first) to indicate that a declared variable can be treated as atomic. See above for an example.
- XFORM_START_SUSPEND and XFORM_END_SUSPEND: for use at the top level (outside of any function definition), and similar to XFORM_START_SKIP and XFORM_END_SKIP in that function and class bodies are not transformed. Type and prototype information is still collected for use by later transformations, however. These forms must be terminated by a semi-colon.
- XFORM_START_TRUST_ARITH and XFORM_END_TRUST_ARITH: for use at the top level (outside of any function definition) to disable warnings about pointer arithmetic. Use only when you're absolutely certain that the garbage collector cannot be pointers offset into the middle of a collectable object. These forms must be terminated by a semi-colon.
- XFORM_TRUST_PLUS: a replacement for + that does not trigger pointer-arithmetic warnings. Use with care.
- XFORM_TRUST_MINUS: a replacement for that does not trigger pointer-arithmetic warnings. Use with care.

3.1.5 Places and Garbage Collector Instances

When places are enabled, then a single process can have multiple instances of the garbage collector in the same process. Each place allocates using its own collector, and no place is allowed to hold a reference to memory that is allocated by another place. In addition, a *master* garbage collector instance holds values that are shared among places; different places can refer to memory that is allocated by the master garbage collector, but the master still cannot reference memory allocated by place-specific garbage collectors.

Calling scheme_main_stack_setup creates the master garbage collector, and allocation uses that collector until scheme_basic_env returns, at which point the initial place's garbage collector is in effect. Using scheme_register_static or MZ_REGISTER_STATIC before calling scheme_basic_env registers an address that should be used to hold only values allocated before scheme_basic_env is called. More typically, scheme_register_static and MZ_REGISTER_STATIC are used only after scheme_basic_env returns. Using scheme_main_setup calls scheme_basic_env automatically, in which case there is no opportunity to use scheme_register_static or MZ_REGISTER_STATIC too early.

3.2 Memory Functions

void* scheme_malloc(size_t n)

Allocates n bytes of collectable memory, initially filled with zeros. In 3m, the allocated object is treated as an array of pointers.

void* scheme_malloc_atomic(size_t n)

Allocates *n* bytes of collectable memory containing no pointers visible to the garbage collector. The object is *not* initialized to zeros.

void* scheme_malloc_uncollectable(size_t n)

Non-3m, only. Allocates *n* bytes of uncollectable memory.

```
void* scheme_malloc_eternal(size_t n)
```

Allocates uncollectable atomic memory. This function is equivalent to malloc, except that the memory cannot be freed.

Allocates *num* * *size* bytes of memory using scheme_malloc.

```
void* scheme_malloc_tagged(size_t n)
```

Like scheme_malloc, but in 3m, the type tag determines how the garbage collector traverses the object; see §3 "Memory Allocation".

void* scheme_malloc_allow_interior(size_t n)

Like scheme_malloc, but in 3m, the object never moves, and pointers are allowed to reference the middle of the object; see §3 "Memory Allocation".

```
void* scheme_malloc_atomic_allow_interior(size_t n)
```

Like scheme_malloc_atomic, but in 3m, the object never moves, and pointers are allowed to reference the middle of the object; see §3 "Memory Allocation".

void* scheme_malloc_stubborn(size_t n)

An obsolete variant of scheme_malloc, where scheme_end_stubborn_change can be called on the allocated pointer when no further changes will be made to the allocated memory. Stubborn allocation is potentially useful as a hint for generational collection, but the hint is normally ignored and unlikely to be used more in future version.

```
void* scheme_end_stubborn_change(void* p)
```

Declares the end of changes to the memory at p as allocated via scheme_malloc_stubborn.

char* scheme_strdup(char* str)

Copies the null-terminated string str; the copy is collectable.

char* scheme_strdup_eternal(char* str)

Copies the null-terminated string *str*; the copy will never be freed.

Attempts to allocate *size* bytes using *mallocf*. If the allocation fails, the exn:misc:out-of-memory exception is raised.

void** scheme_malloc_immobile_box(void* p)

Allocates memory that is not garbage-collected and that does not move (even with 3m), but whose first word contains a pointer to a collectable object. The box is initialized with p, but the value can be changed at any time. An immobile box must be explicitly freed using scheme_free_immobile_box.

```
void scheme_free_immobile_box(void** b)
```

Frees an immobile box allocated with scheme_malloc_immobile_box.

```
void* scheme_malloc_code(intptr_t size)
```

Allocates non-collectable memory to hold executable machine code. Use this function instead of malloc to ensure that the allocated memory has "execute" permissions. Use scheme_free_code to free memory allocated by this function.

```
void scheme_free_code(void* p)
```

Frees memory allocated with scheme_malloc_code.

Registers an extension's global variable that can contain Racket pointers (for the current place). The address of the global is given in *ptr*, and its size in bytes in *size*.

In addition to global variables, this function can be used to register any permanent memory that the collector would otherwise treat as atomic. A garbage collection can occur during the registration.

Initializes the GC stack base, creates the initial namespace by calling scheme_basic_env, and then calls *main* with the namespace, *argc*, and *argv*. (The *argc* and *argv* are just passed

on to main, and are not inspected in any way.)

The Scheme_Env_Main type is defined as follows:

The result of *main* is the result of scheme_main_setup.

If *no_auto_statics* is non-zero, then static variables must be explicitly registered with the garbage collector; see §3 "Memory Allocation" for more information.

A more primitive variant of scheme_main_setup that initializes the GC stack base but does not create the initial namespace (so an embedding application can perform other operations that involve garbage-collected data before creating a namespace).

The *data* argument is passed through to *main*, where the Scheme_Nested_Main type is defined as follows:

Overrides the GC's auto-determined stack base, and/or disables the GC's automatic traversal of global and static variables. If *stack_addr* is NULL, the stack base determined by the GC is used. Otherwise, it should be the "deepest" memory address on the stack where a collectable pointer might be stored. This function should be called only once, and before any other scheme_ function is called, but only with CGC and when future and places are disabled. The function never triggers a garbage collection.

Example:

```
int main(int argc, char **argv) {
    int dummy;
    scheme_set_stack_base(&dummy, 0);
    real_main(argc, argv); /* calls scheme_basic_env(), etc. */
}
```

On 3m, the above code does not quite work, because *stack_addr* must be the beginning or end of a local-frame registration. Worse, in CGC or 3m, if real_main is declared static, the compiler may inline it and place variables containing collectable values deeper in the stack than dummy. To avoid these problems, use scheme_main_setup or scheme_main_stack_setup, instead. The above code also may not work when future and/or places are enabled in Racket, because scheme_set_stack_base does not initialize Racket's thread-local variables. Again, use scheme_main_setup or scheme_main_stack_setup to avoid the problem.

Like scheme_set_stack_base, except for the extra *stack_end* argument. If *stack_end* is non-NULL, then it corresponds to a point of C-stack growth after which Racket should attempt to handle stack overflow. The *stack_end* argument should not correspond to the actual stack end, since detecting stack overflow may take a few frames, and since handling stack overflow requires a few frames.

If *stack_end* is NULL, then the stack end is computed automatically: the stack size assumed to be the limit reported by getrlimit on Unix and Mac OS X, or it is assumed to be the stack reservation of the executable (or 1 MB if parsing the executable fails) on Windows; if this size is greater than 8 MB, then 8 MB is assumed, instead; the size is decremented by 50000 bytes (64-bit Windows: 100000 bytes) to cover a large margin of error; finally, the size is subtracted from (for stacks that grow down) or added to (for stacks that grow up) the stack base in *stack_addr* or the automatically computed stack base. Note that the 50000-byte margin of error is assumed to cover the difference between the actual stack start and the reported stack base, in addition to the margin needed for detecting and handling stack overflow.

Only available on 32-bit Windows; registers *ptr* as the address of a thread-local pointer variable that is declared in the main executable. The variable's storage will be used to implement thread-local storage within the Racket run-time. See §1.5 "Embedding Racket into a Program".

The *tls_index* argument must be 0. It is currently ignored, but a future version may use the argument to allow declaration of the thread-local variable in a dynamically linked DLL.

Like scheme_register_extension_global, for use in embedding applications in situations where the collector does not automatically find static variables (i.e., when scheme_set_stack_base has been called with a non-zero second argument).

The macro MZ_REGISTER_STATIC can be used directly on a static variable. It expands to a comment if statics need not be registered, and a call to scheme_register_static (with the address of the static variable) otherwise.

```
void scheme_weak_reference(void** p)
```

Registers the pointer p as a weak pointer; when no other (non-weak) pointers reference the same memory as p references, then p will be set to NULL by the garbage collector. The value in p may change, but the pointer remains weak with respect to the value of p at the time p was registered.

This function is not available in 3m.

Like scheme_weak_reference, but p is set to NULL (regardless of its prior value) when there are no references to v.

This function is not available in 3m.

Registers a callback function to be invoked when the memory p would otherwise be garbagecollected, and when no "will"-like finalizers are registered for p.

The fnl_proc type is not actually defined, but it is equivalent to

typedef void (*fnl_proc)(void *p, void *data)

The *f* argument is the callback function; when it is called, it will be passed the value *p* and the data pointer *data*; *data* can be anything — it is only passed on to the callback function. If *oldf* and *olddata* are not NULL, then **oldf* and **olddata* are filled with the old callback information (*f* and *data* will override this old callback).

To remove a registered finalizer, pass NULL for f and *data*.

Note: registering a callback not only keeps *p* from collection until the callback is invoked, but it also keeps *data* reachable until the callback is invoked.

Adds a finalizer to a chain of primitive finalizers. This chain is separate from the single finalizer installed with scheme_register_finalizer; all finalizers in the chain are called immediately after a finalizer that is installed with scheme_register_finalizer.

See scheme_register_finalizer, above, for information about the arguments.

To remove an added finalizer, use scheme_subtract_finalizer.

Installs a "will"-like finalizer, similar to will-register. Will-like finalizers are called one at a time, requiring the collector to prove that a value has become inaccessible again before calling the next will-like finalizer. Finalizers registered with scheme_register_finalizer or scheme_add_finalizer are not called until all willlike finalizers have been exhausted.

See scheme_register_finalizer, above, for information about the arguments.

There is currently no facility to remove a will-like finalizer.

Like scheme_add_finalizer, but if the combination *f* and *data* is already registered as a (non-"will"-like) finalizer for *p*, it is not added a second time.

Like scheme_add_scheme_finalizer, but if the combination of f and *data* is already registered as a "will"-like finalizer for p, it is not added a second time.

Removes a finalizer that was installed with scheme_add_finalizer.

```
void scheme_remove_all_finalization(void* p)
```

Removes all finalization ("will"-like or not) for *p*, including wills added in Scheme with will-register and finalizers used by custodians.

void scheme_dont_gc_ptr(void* p)

Keeps the collectable block p from garbage collection. Use this procedure when a reference to p is be stored somewhere inaccessible to the collector. Once the reference is no longer used from the inaccessible region, de-register the lock with scheme_gc_ptr_ok. A garbage collection can occur during the registration.

This function keeps a reference count on the pointers it registers, so two calls to $scheme_dont_gc_ptr$ for the same p should be balanced with two calls to

scheme_gc_ptr_ok.

void scheme_gc_ptr_ok(void* p)

See scheme_dont_gc_ptr.

void scheme_collect_garbage()

Forces an immediate garbage-collection.

void scheme_enable_garbage_collection(int on)

Garbage collection is enabled only when an internal counter is 0. Calling scheme_enable_garbage_collection with a false value increments the counter, and calling scheme_enable_garbage_collection with a true value decrements the counter.

When the PLTDISABLEGC environment variable is set, then racket initializes the internal counter to 1 to initially disable garbage collection.

3m only. Registers a size, mark, and fixup procedure for a given type tag; see §3.1.1 "Tagged Objects" for more information.

Each of the three procedures takes a pointer and returns an integer:

```
typedef int (*Size_Proc)(void *obj);
typedef int (*Mark_Proc)(void *obj);
typedef int (*Fixup_Proc)(void *obj);
```

If the result of the size procedure is a constant, then pass a non-zero value for *is_const_size*. If the mark and fixup procedures are no-ops, then pass a non-zero value for *is_atomic*.

```
void* GC_resolve(void* p)
```

3m only. Can be called by a size, mark, or fixup procedure that is registered with $GC_register_traversers$. It returns the current address of an object *p* that might have been moved already, where *p* corresponds to an object that is referenced directly by the object being sized, marked, or fixed. This translation is necessary, for example, if the size or structure of an object depends on the content of an object it references. For example, the size of a class instance usually depends on a field count that is stored in the class. A fixup procedure should call this function on a reference *before* fixing it.

void* GC_fixup_self(void* p)

3m only. Can be called by a fixup procedure that is registered with $GC_register_traversers$. It returns the final address of p, which must be the pointer passed to the fixup procedure. For some implementations of the memory manager, the result is the same as p, either because objects are not moved or because the object is moved before it is fixed. With other implementations, an object might be moved after the fixup process, and the result is the location that the object will have after garbage collection finished.

Registers descriptions of foreign functions to be called just before and just after a garbage collection. The foreign functions must not allocate garbage-collected memory, and they are called in a way that does not allocate, which is why *pre_desc* and *post_desc* are function descriptions instead of thunks.

A description is a vector of vectors, where each of the inner vectors describes a single call, and the calls are performed in sequence. Each call vector starts with a symbol that indicates the protocol of the foreign function to be called. The following protocols are supported:

- 'ptr_ptr_ptr->void corresponds to void (*)(void*, void*, void*).
- 'ptr_ptr_int->void corresponds to void (*)(void*, void*, void*, int).
- 'ptr_ptr_float->void corresponds to void (*)(void*, void*, float).
- 'ptr_ptr_double->void corresponds to void (*)(void*, void*, double).
- 'ptr_ptr_ptr_int_int_int_int_int_int_int_int_>void corresponds to void (*)(void*, void*, void*, int, int, int, int, int, int, int, int).
- 'osapi_ptr_int->void corresponds to void (*)(void*, int), but using the stdcall calling convention on Windows.
- 'osapi_ptr_ptr->void corresponds to void (*)(void*, void*), but using the stdcall calling convention on Windows.
- 'osapi_ptr_int_int_int_ptr_int_int_long->void corresponds to void
 (*)(void*, int, int, int, void*, int, int, long), but using the
 stdcall calling convention on Windows.

After the protocol symbol, the vector should contain a pointer to a foreign function and then an element for each of the function's arguments. Pointer values are represented as for the _pointer representation defined by ffi/unsafe.

The result is a key for use with scheme_remove_gc_callback. If the key becomes inaccessible, then the callback will be removed automatically (but beware that the pre-callback will have executed and the post-callback will not have executed).

void scheme_remove_gc_callback(Scheme_Object* key)

Removes a garbage-collection callback installed with scheme_add_gc_callback.

4 Namespaces and Modules

A Racket namespace (a top-level environment) is represented by a value of type Scheme_Env* — which is also a Racket value, castable to Scheme_Object*. Calling scheme_basic_env returns a namespace that includes all of Racket's standard global procedures and syntax.

The scheme_basic_env function must be called once by an embedding program, before any other Racket function is called (except scheme_make_param), but scheme_main_setup automatically calls scheme_basic_env. The returned namespace is the initial current namespace for the main Racket thread. Racket extensions cannot call scheme_basic_env.

The current thread's current namespace is available from scheme_get_env, given the current parameterization (see §9 "Parameterizations"): scheme_get_env(scheme_config).

New values can be added as globals in a namespace using scheme_add_global. The scheme_lookup_global function takes a Racket symbol and returns the global value for that name, or NULL if the symbol is undefined.

A module's set of top-level bindings is implemented using the same machinery as a namespace. Use scheme_primitive_module to create a new Scheme_Env* that represents a primitive module. The name provided to scheme_primitive_module is subject to change through the current-module-declare-name parameter (which is normally set by the module name resolver when auto-loading module files). After installing variables into the module with scheme_add_global, etc., call scheme_finish_primitive_module on the Scheme_Env* value to make the module declaration available. All defined variables are exported from the primitive module.

The Racket #%variable-reference form produces a value that is opaque to Racket code. Use SCHEME_PTR_VAL on the result of #%variable-reference to obtain the same kind of value as returned by scheme_global_bucket (i.e., a bucket containing the variable's value, or NULL if the variable is not yet defined).

Adds a value to the table of globals for the namespace *env*, where *name* is a null-terminated string. (The string's case will be normalized in the same way as for interning a symbol.)

Adds a value to the table of globals by symbol name instead of string name.

Given a global variable name (as a symbol) in sym, returns the current value.

Given a global variable name (as a symbol) in *sym*, returns the bucket where the value is stored. When the value in this bucket is NULL, then the global variable is undefined.

The Scheme_Bucket structure is defined as:

Like scheme_global_bucket, but finds a variable in a module. The *mod* and *symbol* arguments are as for dynamic-require in Racket. The *pos* argument should be -1 always. The *env* argument represents the namespace in which the module is declared.

Changes the value of a global variable. The *procname* argument is used to report errors (in case the global variable is constant, not yet bound, or bound as syntax). If *set_undef* is not 1, then the global variable must already have a binding. (For example, set! cannot set unbound variables, while define can.)

Scheme_Object* scheme_builtin_value(const char* name)

Gets the binding of a name as it would be defined in the initial namespace.

Scheme_Env* scheme_get_env(Scheme_Config* *config*)

Returns the current namespace for the given parameterization (see §9 "Parameterizations"). The current thread's current parameterization is available as scheme_config.

Scheme_Env* scheme_primitive_module(Scheme_Object* name, Scheme_Env* for_env) Prepares a new primitive module whose name is the symbol *name* (or an alternative that is active via current-module-declare-name). The module will be declared within the namespace *for_env*. The result is a Scheme_Env * value that can be used with scheme_add_global, etc., but it represents a module instead of a namespace. The module is not fully declared until scheme_finish_primitive_module is called, at which point all variables defined in the module become exported.

void scheme_finish_primitive_module(Scheme_Env* env)

Finalizes a primitive module and makes it available for use within the module's namespace.

5 Procedures

A *primitive procedure* is a Racket-callable procedure that is implemented in C. Primitive procedures are created in Racket with the function scheme_make_prim_w_arity, which takes a C function pointer, the name of the primitive, and information about the number of Racket arguments that it takes; it returns a Racket procedure value.

The C function implementing the procedure must take two arguments: an integer that specifies the number of arguments passed to the procedure, and an array of Scheme_Object* arguments. The number of arguments passed to the function will be checked using the arity information. (The arity information provided to scheme_make_prim_w_arity is also used for the Racket arity procedure.) The procedure implementation is not allowed to mutate the input array of arguments; as an exception, the procedure can mutate the array if it is the same as the result of scheme_current_argument_stack. The procedure may mutate the arguments themselves when appropriate (e.g., a fill in a vector argument).

The function scheme_make_prim_closure_w_arity is similar to scheme_make_prim_w_arity, but it takes an additional count and Scheme_Object* array that is copied into the created procedure; the procedure is passed back to the C function when the closure is invoked. In this way, closure-like data from the C world can be associated with the primitive procedure.

The function scheme_make_closed_prim_w_arity is similar to scheme_make_prim_closure_w_arity, but it uses an older calling convention for passing closure data.

To work well with Scheme threads, a C function that performs substantial or unbounded work should occasionally call SCHEME_USE_FUEL; see §8.2 "Allowing Thread Switches" for details.

Creates a primitive procedure value, given the C function pointer *prim*. The form of *prim* is defined by:

The value *mina* should be the minimum number of arguments that must be supplied to the procedure. The value *maxa* should be the maximum number of arguments that can be supplied to the procedure, or -1 if the procedure can take arbitrarily many arguments. The *mina* and *maxa* values are used for automatically checking the argument count before the primitive is invoked, and also for the Racket arity procedure. The *name* argument is used to

report application arity errors at run-time.

Like scheme_make_prim_w_arity, but if *folding* is non-zero, the compiler assumes that an application of the procedure to constant values can be folded to a constant. For example, +, zero?, and string-length are folding primitives, but display and cons are not.

```
Scheme_Object* scheme_make_prim(Scheme_Prim* prim)
```

Same as scheme_make_prim_w_arity, but the arity (0, -1) and the name "UNKNOWN" is assumed. This function is provided for backward compatibility only.

Creates a primitive procedure value that includes the *c* values in *vals*; when the C function *prim* is invoked, the generated primitive is passed as the last parameter. The form of *prim* is defined by:

The macro SCHEME_PRIM_CLOSURE_ELS takes a primitive-closure object and returns an array with the same length and content as *vals*. (3m: see §3.1 "Cooperating with 3m" for a caution about SCHEME_PRIM_CLOSURE_ELS.)

Creates an old-style primitive procedure value; when the C function *prim* is invoked, *data* is passed as the first parameter. The form of *prim* is defined by:

Creates a closed primitive procedure value without arity information. This function is provided for backward compatibility only.

```
Scheme_Object** scheme_current_argument_stack()
```

Returns a pointer to an internal stack for argument passing. When the argument array passed to a procedure corresponds to the current argument stack address, the procedure is allowed to modify the array. In particular, it might clear out pointers in the argument array to allow the arguments to be reclaimed by the memory manager (if they are not otherwise accessible).

6 Evaluation

A Racket S-expression is evaluated by calling scheme_eval. This function takes an S-expression (as a Scheme_Object*) and a namespace and returns the value of the expression in that namespace.

The function scheme_apply takes a Scheme_Object* that is a procedure, the number of arguments to pass to the procedure, and an array of Scheme_Object * arguments. The return value is the result of the application. There is also a function scheme_apply_to_list, which takes a procedure and a list (constructed with scheme_make_pair) and performs the Racket apply operation.

The scheme_eval function actually calls scheme_compile followed by scheme_eval_compiled.

6.1 Top-level Evaluation Functions

The functions scheme_eval, scheme_apply, etc., are *top-level evaluation functions*. Continuation invocations are confined to jumps within a top-level evaluation (i.e., a continuation barrier is installed by these functions).

The functions _scheme_eval_compiled, _scheme_apply, etc. (with a leading underscore) provide the same functionality without starting a new top-level evaluation; these functions should only be used within new primitive procedures. Since these functions allow full continuation hops, calls to non-top-level evaluation functions can return zero or multiple times.

Currently, escape continuations and primitive error escapes can jump out of all evaluation and application functions. For more information, see §7 "Exceptions and Escape Continuations".

6.2 Tail Evaluation

All of Racket's built-in functions and syntax support proper tail-recursion. When a new primitive procedure or syntax is added to Racket, special care must be taken to ensure that tail recursion is handled properly. Specifically, when the final return value of a function is the result of an application, then scheme_tail_apply should be used instead of scheme_apply. When scheme_tail_apply is called, it postpones the procedure application until control returns to the Racket evaluation loop.

For example, consider the following implementation of a thunk-or primitive, which takes any number of thunks and performs or on the results of the thunks, evaluating only as many thunks as necessary.

```
static Scheme_Object *
thunk_or (int argc, Scheme_Object **argv)
{
    int i;
    Scheme_Object *v;
    if (!argc)
       return scheme_false;
    for (i = 0; i < argc - 1; i++)
       if (SCHEME_FALSEP((v = _scheme_apply(argv[i], 0, NULL))))
        return v;
    return scheme_tail_apply(argv[argc - 1], 0, NULL);
}</pre>
```

This thunk-or properly implements tail-recursion: if the final thunk is applied, then the result of thunk-or is the result of that application, so scheme_tail_apply is used for the final application.

6.3 Multiple Values

A primitive procedure can return multiple values by returning the result of calling scheme_values. The functions scheme_eval_compiled_multi, scheme_apply_multi, _scheme_eval_compiled_multi, and _scheme_apply_multi potentially return multiple values; all other evaluation and applications procedures return a single value or raise an exception.

Multiple return values are represented by the scheme_multiple_values "value." This quasi-value has the type Scheme_Object*, but it is not a pointer or a fixnum. When the result of an evaluation or application is scheme_multiple_values, the number of actual values can be obtained as scheme_multiple_count, and the array of Scheme_Object* values as scheme_multiple_array. (Both of those identifiers are actually macros.)

A garbage collection must not occur between the return of a scheme_multiple_values "value" and the receipt of the values through scheme_multiple_count scheme_multiple_array. Furthermore, if scheme_multiple_array is to be used across a potential garbage collection, then it must be specifically received by calling scheme_detach_multiple_array; otherwise, a garbage collection or further evaluation may change the content of the array. Otherwise, if any application or evaluation procedure is called, the scheme_multiple_count and scheme_multiple_array variables may be modified (but the array previously referenced by scheme_multiple_array is never re-used if scheme_detach_multiple_array is called).

The scheme_multiple_count and scheme_multiple_array variables only contain

meaningful values when scheme_multiple_values is returned.

6.4 Evaluation Functions

Evaluates the (uncompiled) S-expression expr in the namespace env.

```
Scheme_Object* scheme_eval_compiled(Scheme_Object* obj,
Scheme_Env* env)
```

Evaluates the compiled expression *obj*, which was previously returned from scheme_compile, first linking to the namespace *env*.

Scheme_Object* scheme_eval_compiled_multi(Scheme_Object* obj, Scheme_Env* env)

Evaluates the compiled expression *obj*, possibly returning multiple values (see §6.3 "Multiple Values").

Non-top-level version of scheme_eval_compiled. (See §6.1 "Top-level Evaluation Functions".)

```
Scheme_Object* _scheme_eval_compiled_multi(Scheme_Object* obj,
Scheme_Env* env)
```

Non-top-level version of scheme_eval_compiled_multi. (See §6.1 "Top-level Evaluation Functions".)

```
Scheme_Env* scheme_basic_env()
```

Creates the main namespace for an embedded Racket. This procedure must be called before other Racket library function (except scheme_make_param). Extensions to Racket cannot call this function.

If it is called more than once, this function resets all threads (replacing the main thread), parameters, ports, namespaces, and finalizations.

Creates and returns a new namespace. This values can be cast to Scheme_Env *. It can also be installed in a parameterization using scheme_set_param with MZCONFIG_ENV.

When Racket is embedded in an application, create the initial namespace with scheme_basic_env before calling this procedure to create new namespaces.

Applies the procedure f to the given arguments.

Beware that the procedure can mutate *args* if it is the same as the result of scheme_current_argument_stack.

Applies the procedure f to the given arguments, possibly returning multiple values (see §6.3 "Multiple Values").

Non-top-level version of scheme_apply. (See §6.1 "Top-level Evaluation Functions".)

Non-top-level version of scheme_apply_multi. (See §6.1 "Top-level Evaluation Functions".)

```
Scheme_Object* scheme_apply_to_list(Scheme_Object* f,
Scheme_Object* args)
```

Applies the procedure *f* to the list of arguments in *args*.

Reads a single S-expression from *str* and evaluates it in the given namespace; the expression must return a single value, otherwise an exception is raised. The *str* argument is parsed as a UTF-8-encoded string of Unicode characters (so plain ASCII is fine).

Like scheme_eval_string, but returns scheme_multiple_values when the expression returns multiple values.

Like scheme_eval_string, but if *all* is not 0, then expressions are read and evaluated from *str* until the end of the string is reached.

Applies the procedure as a tail-call. Actually, this function just registers the given application to be invoked when control returns to the evaluation loop. (Hence, this function is only useful within a primitive procedure that is returning to its caller.)

Like scheme_tail_apply, but the array *args* is not copied. Use this only when *args* has infinite extent and will not be used again, or when *args* will certainly not be used again until the called procedure has returned.

Applies the procedure as a tail-call.

Compiles the S-expression *form* in the given namespace. The returned value can be used with scheme_eval_compiled et al. Provide a non-zero value for *writable* if the resulting compiled object will be marshalled via write instead of evaluated.

Expands all macros in the S-expression form using the given namespace.

Returns the given values together as multiple return values. Unless n is 1, the result will always be scheme_multiple_values.

void scheme_detach_multiple_array(Scheme_Object** args)

Called to receive multiple-value results; see §6.3 "Multiple Values".

7 Exceptions and Escape Continuations

When Racket encounters an error, it raises an exception. The default exception handler invokes the error display handler and then the error escape handler. The default error escape handler escapes via a *primitive error escape*, which is implemented by calling scheme_longjmp(*scheme_current_thread->error_buf).

An embedding program should install a fresh buffer into scheme_current_thread->error_buf and call scheme_setjmp(*scheme_current_thread->error_buf) before any top-level entry into Racket evaluation to catch primitive error escapes. When the new buffer goes out of scope, restore the original in scheme_current_thread->error_buf. The macro scheme_error_buf is a shorthand for *scheme_current_thread->error_buf.

```
mz_jmp_buf * volatile save, fresh;
...
save = scheme_current_thread->error_buf;
scheme_current_thread->error_buf = &fresh;
if (scheme_setjmp(scheme_error_buf)) {
    /* There was an error */
    ...
} else {
    v = scheme_eval_string(s, env);
}
scheme_current_thread->error_buf = save;
...
```

3m: when scheme_setjmp is used, the enclosing context must provide a local-variable registration record via MZ_GC_DECL_REG. Use MZ_GC_DECL_REG(0) if the context has no local variables to register. Unfortunately, when using --xform with raco ctool instead of MZ_GC_DECL_REG, etc., you may need to declare a dummy pointer and use it after scheme_setjmp to ensure that a local-variable registration is generated.

New primitive procedures can raise a generic exception by calling scheme_signal_error. The arguments for scheme_signal_error are roughly the same as for the standard C function printf. A specific primitive exception can be raised by calling scheme_raise_exn.

Full continuations are implemented in Racket by copying the C stack and using scheme_setjmp and scheme_longjmp. As long a C/C++ application invokes Racket evaluation through the top-level evaluation functions (scheme_eval, scheme_apply, etc., as opposed to _scheme_apply, _scheme_eval_compiled, etc.), the code is protected against any unusual behavior from Racket evaluations (such as returning twice from a function) because continuation invocations are confined to jumps within a single top-level evaluation. However, escape continuation jumps are still allowed; as explained in the following subsection, special care must be taken in extension that is sensitive to escapes.

7.1 Temporarily Catching Error Escapes

When implementing new primitive procedure, it is sometimes useful to catch and handle errors that occur in evaluating subexpressions. One way to do this is the following: save scheme_current_thread->error_buf to a temporary variable, set scheme_current_thread->error_buf to the address of a stack-allocated mz_jmp_buf, invoke scheme_setjmp(scheme_error_buf), perform the function's work, and then restore scheme_current_thread->error_buf before returning a value. (3m: A stack-allocated mz_jmp_buf instance need not be registered with the garbage collector, and a heap-allocated mz_jmp_buf should be allocated as atomic.)

However, beware that a prompt abort or the invocation of an escaping continuation looks like a primitive error escape. In that case, the special indicator flag scheme_jumping_to_continuation is non-zero (instead of its normal zero value); this situation is only visible when implementing a new primitive procedure. When scheme_jumping_to_continuation is non-zero, honor the escape request by chaining to the previously saved error buffer; otherwise, call scheme_clear_escape.

```
mz_jmp_buf * volatile save, fresh;
save = scheme_current_thread->error_buf;
scheme_current_thread->error_buf = &fresh;
if (scheme_setjmp(scheme_error_buf)) {
  /* There was an error or continuation invocation */
  if (scheme_jumping_to_continuation) {
    /* It was a continuation jump */
    scheme_longjmp(*save, 1);
    /* To block the jump, instead: scheme_clear_escape(); */
  } else {
    /* It was a primitive error escape */
  }
} else {
  scheme_eval_string("x", scheme_env);
7
scheme_current_thread->error_buf = save;
```

This solution works fine as long as the procedure implementation only calls top-level evaluation functions (scheme_eval, scheme_apply, etc., as opposed to _scheme_apply, _scheme_eval_compiled, etc.). Otherwise, use scheme_dynamic_wind to protect your code against full continuation jumps in the same way that dynamic-wind is used in Racket.

The above solution simply traps the escape; it doesn't report the reason that the escape occurred. To catch exceptions and obtain information about the exception, the simplest route is to mix Racket code with C-implemented thunks. The code below can be used to catch exceptions in a variety of situations. It implements the function _ap-ply_catch_exceptions, which catches exceptions during the application of a thunk. (This code is in "collects/mzscheme/examples/catch.c" in the distribution.)

```
static Scheme_Object *exn_catching_apply, *exn_p, *exn_message;
  static void init_exn_catching_apply()
  {
    if (!exn_catching_apply) {
      char *e =
        "(lambda (thunk) "
          "(with-handlers ([void (lambda (exn) (cons #f exn))]) "
            "(cons #t (thunk))))";
      /* make sure we have a namespace with the standard bindings: */
      Scheme_Env *env = (Scheme_Env *)scheme_make_namespace(0, NULL);
      scheme_register_extension_global(&exn_catching_apply,
                                       sizeof(Scheme_Object *));
      scheme_register_extension_global(&exn_p,
                                       sizeof(Scheme_Object *));
      scheme_register_extension_global(&exn_message,
                                       sizeof(Scheme_Object *));
      exn_catching_apply = scheme_eval_string(e, env);
      exn_p = scheme_lookup_global(scheme_intern_symbol("exn?"),
env);
      exn_message
        = scheme_lookup_global(scheme_intern_symbol("exn-message"),
                               env);
   }
  }
  /* This function applies a thunk, returning the Racket value if
     there's no exception, otherwise returning NULL and setting *exn
     to the raised value (usually an exn structure). */
  Scheme_Object *_apply_thunk_catch_exceptions(Scheme_Object *f,
                                               Scheme_Object **exn)
  {
   Scheme_Object *v;
   init_exn_catching_apply();
    v = _scheme_apply(exn_catching_apply, 1, &f);
    /* v is a pair: (cons #t value) or (cons #f exn) */
    if (SCHEME_TRUEP(SCHEME_CAR(v)))
      return SCHEME_CDR(v);
    else {
      *exn = SCHEME_CDR(v);
      return NULL;
```

```
}
}
Scheme_Object *extract_exn_message(Scheme_Object *v)
{
    init_exn_catching_apply();
    if (SCHEME_TRUEP(_scheme_apply(exn_p, 1, &v)))
        return _scheme_apply(exn_message, 1, &v);
    else
        return NULL; /* Not an exn structure */
}
```

In the following example, the above code is used to catch exceptions that occur during while evaluating source code from a string.

```
static Scheme_Object *do_eval(void *s, int noargc,
                              Scheme_Object **noargv)
{
  return scheme_eval_string((char *)s,
                            scheme_get_env(scheme_config));
}
static Scheme_Object *eval_string_or_get_exn_message(char *s)
ſ
  Scheme_Object *v, *exn;
  v = scheme_make_closed_prim(do_eval, s);
  v = _apply_thunk_catch_exceptions(v, &exn);
  /* Got a value? */
  if (v)
   return v;
  v = extract_exn_message(exn);
  /* Got an exn? */
  if (v)
    return v;
  /* 'raise' was called on some arbitrary value */
  return exn;
}
```

7.2 Enabling and Disabling Breaks

When embedding Racket, asynchronous break exceptions are disabled by default. Call scheme_set_can_break (which is the same as calling the Racket function break-enabled) to enable or disable breaks. To enable or disable breaks during the dynamic extent of another evaluation (where you would use call-with-break-parameterization in Racket), use scheme_push_break_enable before and scheme_pop_break_enable after, instead.

7.3 Exception Functions

Raises a generic primitive exception. The parameters are roughly as for printf, but with the following format directives:

- %c : a Unicode character (of type mzchar)
- <mark>%d</mark> : an int
- %o : an int formatted in octal
- %gd : a long integer
- %gx : a long integer formatted in hexadecimal
- %1d : an intptr_t integer
- %1x : an intptr_t integer formatted in hexadecimal
- %f : a floating-point double
- %s : a nul-terminated char string
- %5 : a nul-terminated mzchar string
- **%S** : a Racket symbol (a Scheme_Object*)
- **%t** : a char string with a intptr_t size (two arguments), possibly containing a nonterminating nul byte, and possibly without a nul-terminator
- **%u** : a mzchar string with a intptr_t size (two arguments), possibly containing a non-terminating nul character, and possibly without a nul-terminator
- %T : a Racket string (a Scheme_Object*)
- ¹/₄ : a string, truncated to 253 characters, with ellipses printed if the string is truncated

- %Q: a Racket string (a Scheme_Object*), truncated to 253 characters, with ellipses printed if the string is truncated
- %V : a Racket value (a Scheme_Object*), truncated according to the current error print width.
- **%D** : a Racket value (a Scheme_Object*), to display.
- % : a Racket value (a Scheme_Object*), that is a list whose printed elements are spliced into the result.
- % e : an errno value, to be printed as a text message.
- % E : a platform-specific error value, to be printed as a text message.
- ¹/_X : a potential platform-specific error value and a char string; if the string is non-NULL, then the error value is ignored, otherwise the error value is used as for ¹/_E.
- %% : a percent sign
- %_ : a pointer to ignore
- %- : an int to ignore

The arguments following the format string must include no more than 25 strings and Racket values, 25 integers, and 25 floating-point numbers. (This restriction simplifies the implementation with precise garbage collection.)

Raises a specific primitive exception. The *exnid* argument specifies the exception to be raised. If an instance of that exception has n fields, then the next n-2 arguments are values for those fields (skipping the message and debug-info fields). The remaining arguments start with an error string and proceed roughly as for printf; see scheme_signal_error above for more details.

Exception ids are #defined using the same names as in Racket, but prefixed with "MZ", all letters are capitalized, and all ":'s', "-"s, and "/"s are replaced with underscores. For example, MZEXN_FAIL_FILESYSTEM is the exception id for a filesystem exception.

This function is automatically invoked when the wrong number of arguments are given to a primitive procedure. It signals that the wrong number of parameters was received and escapes (like scheme_signal_error). The *name* argument is the name of the procedure that was given the wrong number of arguments; *minc* is the minimum number of expected arguments; *maxc* is the maximum number of expected arguments, or -1 if there is no maximum; *argc* and *argv* contain all of the received arguments.

Signals that an argument was received that does not satisfy a contract and escapes (like scheme_signal_error). The *name* argument is the name of the procedure that was given the wrong argument; *expected* is the contract; *which* is the offending argument in the *argv* array; *argc* and *argv* contain all of the received arguments. If the original *argc* and *argv* are not available, provide -1 for *which* and a pointer to the bad value in *argv*, in which case the magnitude (but not sign) of *argc* is ignored. Negate *argc* if the exception corresponds to a result contract instead of an argument contract.

Signals that an argument of the wrong type was received and escapes. Use scheme_wrong_contract, instead.

The arguments are the same as for scheme_wrong_contract, except that *expected* is the name of the expected type.

Signals that the wrong number of values were returned to a multiple-values context. The *expected* argument indicates how many values were expected, *got* indicates the number received, and *argv* are the received values. The *detail* string can be NULL or it can contain a printf-style string (with additional arguments) to describe the context of the error; see scheme_signal_error above for more details about the printf-style string.

void scheme_unbound_global(char* *name*)

Signals an unbound-variable error, where *name* is the name of the variable.

Raises a contract-violation exception. The *msg* string is static, instead of a format string. After *msg*, any number of triples can be provided to add fields (each on its own line) to the error message; each triple is a string for the field name, a 0 or 1 to indicate whether the field value is a literal string or a Racket value, and either a literal string or a Racket value. The sequence of field triples must be terminated with NULL.

Converts a Racket value into a string for the purposes of reporting an error message. The *count* argument specifies how many Racket values total will appear in the error message (so the string for this value can be scaled appropriately). If *len* is not NULL, it is filled with the length of the returned string.

Converts an array of Racket values into a byte string, skipping the array element indicated by *which* if *which* is not -1. This function is used to format the "other" arguments to a function when one argument is bad (thus giving the user more information about the state of the program when the error occurred). If *len* is not NULL, it is filled with the length of the returned string.

If the arguments are shown on multiple lines, then the result string starts with a newline character and each line is indented by three spaces. Otherwise, the result string starts with a space. If the result would contain no arguments, it contains [none], instead.

Like scheme_make_arg_lines_string, but for old-style messages where the arguments are always shown within a single line. The result does not include a leading space.

void scheme_check_proc_arity(char* where,

```
int a,
int which,
int argc,
Scheme_Object** argv)
```

Checks the *which*th argument in *argv* to make sure it is a procedure that can take *a* arguments. If there is an error, the *where*, *which*, *argc*, and *argv* arguments are passed on to scheme_wrong_type. As in scheme_wrong_type, *which* can be -1, in which case **argv* is checked.

Evaluates calls the function *action* to get a value for the scheme_dynamic_wind call. The Pre_Post_Proc and Action_Proc types are not actually defined; instead the types are inlined as if they were defined as follows:

```
typedef void (*Pre_Post_Proc)(void *data);
typedef Scheme_Object* (*Action_Proc)(void *data);
```

The functions pre and post are invoked when jumping into and out of action, respectively.

The function *jmp_handler* is called when an error is signaled (or an escaping continuation is invoked) during the call to *action*; if *jmp_handler* returns NULL, then the error is passed on to the next error handler, otherwise the return value is used as the return value for the scheme_dynamic_wind call.

The pointer *data* can be anything; it is passed along in calls to *action*, *pre*, *post*, and *jmp_handler*.

```
void scheme_clear_escape()
```

Clears the "jumping to escape continuation" flag associated with a thread. Call this function when blocking escape continuation hops (see the first example in §7.1 "Temporarily Catching Error Escapes").

void scheme_set_can_break(int on)

Enables or disables breaks in the same way as calling break-enabled.

Use this function with scheme_pop_break_enable to enable or disable breaks in the same

way as call-with-break-parameterization; this function writes to *cframe* to initialize it, and scheme_pop_break_enable reads from *cframe*. If *pre_check* is non-zero and breaks are currently enabled, any pending break exception is raised.

Use this function with scheme_push_break_enable. If *post_check* is non-zero and breaks are enabled after restoring the previous state, then any pending break exception is raised.

```
Scheme_Object*
scheme_current_continuation_marks(Scheme_Object* prompt_tag)
```

Like current-continuation-marks. Passing NULL as *prompt_tag* is the same as providing the default continuation prompt tag.

Writes a warning message. The parameters are roughly as for printf; see scheme_signal_error above for more details.

Normally, Racket's logging facilities should be used instead of this function.

8 Threads

The initializer function scheme_basic_env creates the main Racket thread; all other threads are created through calls to scheme_thread.

Information about each internal Racket thread is kept in a Scheme_Thread structure. A pointer to the current thread's structure is available as scheme_current_thread. A Scheme_Thread structure includes the following fields:

- error_buf the mz_jmp_buf value used to escape from errors. The error_buf value of the current thread is available as scheme_error_buf.
- cjs.jumping_to_continuation a flag that distinguishes escaping-continuation invocations from error escapes. The cjs.jumping_to_continuation value of the current thread is available as scheme_jumping_to_continuation.
- init_config the thread's initial parameterization. See also §9 "Parameterizations".
- cell_values The thread's values for thread cells (see also §9 "Parameterizations").
- next The next thread in the linked list of threads; this is NULL for the main thread.

The list of all scheduled threads is kept in a linked list; scheme_first_thread points to the first thread in the list. The last thread in the list is always the main thread.

8.1 Integration with Threads

Racket's threads can break external C code under two circumstances:

- *Pointers to stack-based values can be communicated between threads.* For example, if thread A stores a pointer to a stack-based variable in a global variable, if thread B uses the pointer in the global variable, it may point to data that is not currently on the stack.
- *C* functions that can invoke Racket (and also be invoked by Racket) depend on strict function-call nesting. For example, suppose a function F uses an internal stack, pushing items on to the stack on entry and popping the same items on exit. Suppose also that F invokes Racket to evaluate an expression. If the evaluation of this expression invokes F again in a new thread, but then returns to the first thread before completing the second F, then F's internal stack will be corrupted.

If either of these circumstances occurs, Racket will probably crash.

8.2 Allowing Thread Switches

C code that performs substantial or unbounded work should occasionally call SCHEME_USE_FUEL—actually a macro—which allows Racket to swap in another Racket thread to run, and to check for breaks on the current thread. In particular, if breaks are enabled, then SCHEME_USE_FUEL may trigger an exception.

The macro consumes an integer argument. On most platforms, where thread scheduling is based on timer interrupts, the argument is ignored. On some platforms, however, the integer represents the amount of "fuel" that has been consumed since the last call to SCHEME_USE_FUEL. For example, the implementation of vector->list consumes a unit of fuel for each created cons cell:

```
Scheme_Object *scheme_vector_to_list(Scheme_Object *vec)
{
    int i;
    Scheme_Object *pair = scheme_null;
    i = SCHEME_VEC_SIZE(vec);
    for (; i--; ) {
        SCHEME_USE_FUEL(1);
        pair = scheme_make_pair(SCHEME_VEC_ELS(vec)[i], pair);
    }
    return pair;
}
```

The SCHEME_USE_FUEL macro expands to a C block, not an expression.

8.3 Blocking the Current Thread

Embedding or extension code sometimes needs to block, but blocking should allow other Racket threads to execute. To allow other threads to run, block using scheme_block_until. This procedure takes two functions: a polling function that tests whether the blocking operation can be completed, and a prepare-to-sleep function that sets bits in fd_sets when Racket decides to sleep (because all Racket threads are blocked). On Windows, an "fd_set" can also accommodate OS-level semaphores or other handles via scheme_add_fd_handle.

Since the functions passed to scheme_block_until are called by the Racket thread scheduler, they must never raise exceptions, call scheme_apply, or trigger the evaluation of Racket code in any way. The scheme_block_until function itself may call the current exception handler, however, in reaction to a break (if breaks are enabled). When a blocking operation is associated with an object, then the object might make sense as an argument to sync. To extend the set of objects accepted by sync, either register polling and sleeping functions with scheme_add_evt, or register a semaphore accessor with scheme_add_evt_through_sema.

The scheme_signal_received function can be called to wake up Racket when it is sleeping. In particular, calling scheme_signal_received ensures that Racket will poll all blocking synchronizations soon afterward. Furthermore, scheme_signal_received can be called from any OS-level thread. Thus, when no adequate prepare-to-sleep function can be implemented for scheme_block_until in terms of file descriptors or Windows handles, calling scheme_signal_received when the poll result changes will ensure that a poll is issued.

8.4 Threads in Embedded Racket with Event Loops

When Racket is embedded in an application with an event-based model (i.e., the execution of Racket code in the main thread is repeatedly triggered by external events until the application exits) special hooks must be set to ensure that non-main threads execute correctly. For example, during the execution in the main thread, a new thread may be created; the new thread may still be running when the main thread returns to the event loop, and it may be arbitrarily long before the main thread continues from the event loop. Under such circumstances, the embedding program must explicitly allow Racket to execute the non-main threads; this can be done by periodically calling the function scheme_check_threads.

Thread-checking only needs to be performed when non-main threads exist (or when there are active callback triggers). The embedding application can set the global function pointer scheme_notify_multithread to a function that takes an integer parameter and returns void. This function is be called with 1 when thread-checking becomes necessary, and then with 0 when thread checking is no longer necessary. An embedding program can use this information to prevent unnecessary scheme_check_threads polling.

The below code illustrates how GRacket formerly set up scheme_check_threads polling using the wxWindows wxTimer class. (Any regular event-loop-based callback is appropriate.) The scheme_notify_multithread pointer is set to MrEdInstallThreadTimer. (GRacket no longer work this way, however.)

```
class MrEdThreadTimer : public wxTimer
{
   public:
    void Notify(void); /* callback when timer expires */
};
static int threads_go;
static MrEdThreadTimer *theThreadTimer;
#define THREAD_WAIT_TIME 40
```

```
void MrEdThreadTimer::Notify()
{
  if (threads_go)
    Start(THREAD_WAIT_TIME, TRUE);
  scheme_check_threads();
}
static void MrEdInstallThreadTimer(int on)
ſ
  if (!theThreadTimer)
    theThreadTimer = new MrEdThreadTimer;
 if (on)
    theThreadTimer->Start(THREAD_WAIT_TIME, TRUE);
  else
    theThreadTimer->Stop();
  threads_go = on;
  if (on)
    do_this_time = 1;
}
```

An alternate architecture, which GRacket now uses, is to send the main thread into a loop, which blocks until an event is ready to handle. Racket automatically takes care of running all threads, and it does so efficiently because the main thread blocks on a file descriptor, as explained in §8.3 "Blocking the Current Thread".

8.4.1 Callbacks for Blocked Threads

Racket threads are sometimes blocked on file descriptors, such as an input file or the X event socket. Blocked non-main threads do not block the main thread, and therefore do not affect the event loop, so scheme_check_threads is sufficient to implement this case correctly. However, it is wasteful to poll these descriptors with scheme_check_threads when nothing else is happening in the application and when a lower-level poll on the file descriptors can be installed. If the global function pointer scheme_wakeup_on_input is set, then this case is handled more efficiently by turning off thread checking and issuing a "wakeup" request on the blocking file descriptors through scheme_wakeup_on_input.

A scheme_wakeup_on_input procedure takes a pointer to an array of three fd_sets (use MZ_FD_SET instead of FD_SET, etc.) and returns void. The scheme_wakeup_on_input function does not sleep immediately; it just sets up callbacks on the specified file descriptors. When input is ready on any of those file descriptors, the callbacks are removed and

scheme_wake_up is called.

For example, the X Windows version of GRacket formerly set scheme_wakeup_on_input to this MrEdNeedWakeup:

```
static XtInputId *scheme_cb_ids = NULL;
static int num_cbs;
static void MrEdNeedWakeup(void *fds)
{
 int limit, count, i, p;
 fd_set *rd, *wr, *ex;
 rd = (fd_set *)fds;
 wr = ((fd_set *)fds) + 1;
 ex = ((fd_set *)fds) + 2;
 limit = getdtablesize();
 /* See if we need to do any work, really: */
  count = 0;
 for (i = 0; i < limit; i++) {</pre>
    if (MZ_FD_ISSET(i, rd))
      count++;
    if (MZ_FD_ISSET(i, wr))
      count++;
    if (MZ_FD_ISSET(i, ex))
      count++;
 }
 if (!count)
    return;
  /* Remove old callbacks: */
 if (scheme_cb_ids)
    for (i = 0; i < num_cbs; i++)</pre>
      notify_set_input_func((Notify_client)NULL, (Notify_func)NULL,
                             scheme_cb_ids[i]);
 num_cbs = count;
 scheme_cb_ids = new int[num_cbs];
 /* Install callbacks */
 p = 0;
 for (i = 0; i < limit; i++) {</pre>
    if (MZ_FD_ISSET(i, rd))
```

```
scheme_cb_ids[p++] = XtAppAddInput(wxAPP_CONTEXT, i,
                                             (XtPointer *)XtInputRead-
Mask,
                                             (XtInputCallbackProc)MrEdWakeUp,
NULL);
      if (MZ_FD_ISSET(i, wr))
        scheme_cb_ids[p++] = XtAppAddInput(wxAPP_CONTEXT, i,
                                             (XtPointer *)XtIn-
putWriteMask,
                                             (XtInputCallbackProc)MrEdWakeUp,
NULL);
      if (MZ_FD_ISSET(i, ex))
        scheme_cb_ids[p++] = XtAppAddInput(wxAPP_CONTEXT, i,
                                             (XtPointer *)XtInputEx-
ceptMask,
                                             (XtInputCallbackProc)MrEdWakeUp,
                                            NULL);
    }
  }
  /* callback function when input/exception is detected: */
  Bool MrEdWakeUp(XtPointer, int *, XtInputId *)
  {
    int i;
    if (scheme_cb_ids) {
      /* Remove all callbacks: */
      for (i = 0; i < num_cbs; i++)</pre>
       XtRemoveInput(scheme_cb_ids[i]);
      scheme_cb_ids = NULL;
      /* ''wake up'' */
      scheme_wake_up();
    }
    return FALSE;
  }
```

8.5 Sleeping by Embedded Racket

When all Racket threads are blocked, Racket must "sleep" for a certain number of seconds or until external input appears on some file descriptor. Generally, sleeping should block the main event loop of the entire application. However, the way in which sleeping is performed may depend on the embedding application. The global function pointer scheme_sleep can be set by an embedding application to implement a blocking sleep, although Racket implements this function for you.

A scheme_sleep function takes two arguments: a float and a void*. The latter is really points to an array of three "fd_set" records (one for read, one for write, and one for exceptions); these records are described further below. If the float argument is non-zero, then the scheme_sleep function blocks for the specified number of seconds, at most. The scheme_sleep function should block until there is input one of the file descriptors specified in the "fd_set," indefinitely if the float argument is zero.

The second argument to scheme_sleep is conceptually an array of three fd_set records, but always use scheme_get_fdset to get anything other than the zeroth element of this array, and manipulate each "fd_set" with MZ_FD_SET, MZ_FD_CLR, etc. instead of FD_SET, FD_CLR, etc.

The following function mzsleep is an appropriate scheme_sleep function for most any Unix or Windows application. (This is approximately the built-in sleep used by Racket.)

```
void mzsleep(float v, void *fds)
{
 if (v) {
    sleep(v);
  } else {
    int limit;
    fd_set *rd, *wr, *ex;
# ifdef WIN32
    limit = 0;
# else
    limit = getdtablesize();
# endif
    rd = (fd_set *)fds;
    wr = (fd_set *)scheme_get_fdset(fds, 1);
    ex = (fd_set *)scheme_get_fdset(fds, 2);
    select(limit, rd, wr, ex, NULL);
 }
}
```

8.6 Thread Functions

Scheme_Object* scheme_thread(Scheme_Object* *thunk*)

Creates a new thread, just like thread.

Like scheme_thread, except that the created thread belongs to *cust* instead of the current custodian, it uses the given *config* for its initial configuration, it uses *cells* for its thread-cell table, and if *suspend_to_kill* is non-zero, then the thread is merely suspended when it would otherwise be killed (through either kill-thread or custodian-shutdown-all).

The *config* argument is typically obtained through scheme_current_config or scheme_extend_config. A *config* is immutable, so different threads can safely use the same value. The *cells* argument should be obtained from scheme_inherit_cells; it is mutable, and a particular cell table should be used by only one thread.

Scheme_Object* scheme_make_sema(intptr_t v)

Creates a new semaphore.

void scheme_post_sema(Scheme_Object* sema)

Posts to sema.

Waits on *sema*. If *try* is not 0, the wait can fail and 0 is returned for failure, otherwise 1 is returned.

void scheme_thread_block(float sleep_time)

Allows the current thread to be swapped out in favor of other threads. If *sleep_time* positive, then the current thread will sleep for at least *sleep_time* seconds.

After calling this function, a program should almost always call scheme_making_progress next. The exception is when scheme_thread_block is called in a polling loop that performs no work that affects the progress of other threads. In that case, scheme_making_progress should be called immediately after exiting the loop.

See also scheme_block_until, and see also the SCHEME_USE_FUEL macro in §8.2 "Allowing Thread Switches".

Like scheme_thread_block, but breaks are enabled while blocking if *break_on* is true.

void scheme_swap_thread(Scheme_Thread* *thread*)

Swaps out the current thread in favor of thread.

void scheme_break_thread(Scheme_Thread* thread)

Sends a break signal to the given thread.

int scheme_break_waiting(Scheme_Thread* *thread*)

Returns 1 if a break from break-thread or scheme_break_thread has occurred in the specified thread but has not yet been handled.

The Scheme_Ready_Fun and Scheme_Needs_Wakeup_Fun types are defined as follows:

Blocks the current thread until f with *data* returns a true value. The f function is called periodically—at least once per potential swap-in of the blocked thread—and it may be called multiple times even after it returns a true value. If f with *data* ever returns a true value, it must continue to return a true value until scheme_block_until returns. The argument to f is the same *data* as provided to scheme_block_until, and *data* is ignored otherwise. (The *data* argument is not actually required to be a Scheme_Object* value, because it is only used by f and fdf.)

If Racket decides to sleep, then the *fdf* function is called to sets bits in *fds*, conceptually an array of three fd_sets: one or reading, one for writing, and one for exceptions. Use scheme_get_fdset to get elements of this array, and manipulate an "fd_set" with MZ_FD_SET instead of FD_SET, etc. On Windows, an "fd_set" can also accommodate OSlevel semaphores or other handles via scheme_add_fd_handle.

The *fdf* argument can be NULL, which implies that the thread becomes unblocked (i.e., *ready* changes its result to true) only through Racket actions, and never through external processes (e.g., through a socket or OS-level semaphore)—with the exception that scheme_signal_received may be called to indicate an external change.

If *sleep* is a positive number, then scheme_block_until polls *f* at least every *sleep* seconds, but scheme_block_until does not return until *f* returns a true value. The call to scheme_block_until can return before *sleep* seconds if *f* returns a true value.

The return value from scheme_block_until is the return value of its most recent call to *f*, which enables *f* to return some information to the scheme_block_until caller.

See §8.3 "Blocking the Current Thread" for information about restrictions on the f and fdf functions.

Like scheme_block_until, but breaks are enabled while blocking if *break_on* is true.

Like scheme_block_until_enable_break, but the function returns if *unless_evt* becomes ready, where *unless_evt* is a port progress event implemented by scheme_progress_evt_via_get. See scheme_make_input_port for more information.

```
void scheme_signal_received()
```

Indicates that an external event may have caused the result of a synchronization poll to have a different result. Unlike most other Racket functions, this one can be called from any OS-level thread, and it wakes up if the Racket thread if it is sleeping.

```
void scheme_check_threads()
```

This function is periodically called by the embedding program to give background processes time to execute. See §8.4 "Threads in Embedded Racket with Event Loops" for more information.

As long as some threads are ready, this functions returns only after one thread quantum, at least.

```
void scheme_wake_up()
```

This function is called by the embedding program when there is input on an external file descriptor. See §8.5 "Sleeping by Embedded Racket" for more information.

Extracts an "fd_set" from an array passed to scheme_sleep, a callback for scheme_block_until, or an input port callback for scheme_make_input_port.

Adds an OS-level semaphore (Windows) or other waitable handle (Windows) to the "fd_set" *fds*. When Racket performs a "select" to sleep on *fds*, it also waits on the given semaphore or handle. This feature makes it possible for Racket to sleep until it is awakened by an external process.

Racket does not attempt to deallocate the given semaphore or handle, and the "select" call using fds may be unblocked due to some other file descriptor or handle in fds. If *repost* is a true value, then h must be an OS-level semaphore, and if the "select" unblocks due to a post on h, then h is reposted; this allows clients to treat fds-installed semaphores uniformly, whether or not a post on the semaphore was consumed by "select".

The scheme_add_fd_handle function is useful for implementing the second procedure passed to scheme_wait_until, or for implementing a custom input port.

On Unix and Mac OS X, this function has no effect.

Adds an OS-level event type (Windows) to the set of types in the "fd_set" *fds*. When Racket performs a "select" to sleep on *fds*, it also waits on events of them specified type. This feature makes it possible for Racket to sleep until it is awakened by an external process.

The event mask is only used when some handle is installed with scheme_add_fd_handle. This awkward restriction may force you to create a dummy semaphore that is never posted.

On Unix, and Mac OS X, this function has no effect.

The argument types are defined as follows:

Extends the set of waitable objects for sync to those with the type tag *type*. If *filter* is non-NULL, it constrains the new waitable set to those objects for which *filter* returns a non-zero value.

The *ready* and *wakeup* functions are used in the same way was the arguments to scheme_block_until.

The *can_redirect* argument should be 0.

Like scheme_add_evt, but for objects where waiting is based on a semaphore. Instead of *ready* and *wakeup* functions, the *getsema* function extracts a semaphore for a given object:

If a successful wait should leave the semaphore waited, then *getsema* should set **repost* to 0. Otherwise, the given semaphore will be re-posted after a successful wait. A *getsema* function should almost always set **repost* to 1.

```
void scheme_making_progress()
```

Notifies the scheduler that the current thread is not simply calling scheme_thread_block in a loop, but that it is actually making progress.

```
int scheme_tls_allocate()
```

Allocates a thread local storage index to be used with scheme_tls_set and scheme_tls_get.

Stores a thread-specific value using an index allocated with scheme_tls_allocate.

```
void* scheme_tls_get(int index)
```

Retrieves a thread-specific value installed with scheme_tls_set. If no thread-specific value is available for the given index, NULL is returned.

Calls prim with the given argc and argv with breaks enabled. The prim function can block,

in which case it might be interrupted by a break. The *prim* function should not block, yield, or check for breaks after it succeeds, where "succeeds" depends on the operation. For example, tcp-accept/enable-break is implemented by wrapping this function around the implementation of tcp-accept; the tcp-accept implementation does not block or yield after it accepts a connection.

Prevents Racket thread swaps until scheme_end_atomic or scheme_end_atomic_no_swap is called. Start-atomic and end-atomic pairs can be nested.

```
void scheme_end_atomic()
```

Ends an atomic region with respect to Racket threads. The current thread may be swapped out immediately (i.e., the call to scheme_end_atomic is assumed to be a safe point for thread swaps).

```
void scheme_end_atomic_no_swap()
```

Ends an atomic region with respect to Racket threads, and also prevents an immediate thread swap. (In other words, no Racket thread swaps will occur until a future safe point.)

Registers a callback to be invoked just after a Racket thread is swapped in. The *data* is provided back to f when it is called, where Closure_Func is defined as follows:

```
typedef Scheme_Object *(*Scheme_Closure_Func)(Scheme_Object *);
```

Like scheme_add_swap_callback, but registers a callback to be invoked just before a Racket thread is swapped out.

9 Parameterizations

A *parameterization* is a set of parameter values. Each thread has its own initial parameterization, which is extended functionally and superseded by parameterizations that are attached to a particular continuation mark.

Parameterization information is stored in a Scheme_Config record. For the currently executing thread, scheme_current_config returns the current parameterization.

To obtain parameter values, a Scheme_Config is combined with the current threads Scheme_Thread_Cell_Table, as stored in the thread record's cell_values field.

Parameter values for built-in parameters are obtained and modified (for the current thread) using scheme_get_param and scheme_set_param. Each parameter is stored as a Scheme_Object * value, and the built-in parameters are accessed through the following indices:

- MZCONFIG_ENV current-namespace (use scheme_get_env)
- MZCONFIG_INPUT_PORT current-input-port
- MZCONFIG_OUTPUT_PORT current-output-port
- MZCONFIG_ERROR_PORT current-error-port
- MZCONFIG_ERROR_DISPLAY_HANDLER error-display-handler
- MZCONFIG_ERROR_PRINT_VALUE_HANDLER error-value->string-handler
- MZCONFIG_EXIT_HANDLER exit-handler
- MZCONFIG_INIT_EXN_HANDLER uncaught-exception-handler
- MZCONFIG_EVAL_HANDLER current-eval
- MZCONFIG_LOAD_HANDLER current-load
- MZCONFIG_PRINT_HANDLER current-print
- MZCONFIG_PROMPT_READ_HANDLER current-prompt-read
- MZCONFIG_CAN_READ_GRAPH read-accept-graph
- MZCONFIG_CAN_READ_COMPILED read-accept-compiled
- MZCONFIG_CAN_READ_BOX read-accept-box
- MZCONFIG_CAN_READ_PIPE_QUOTE read-accept-bar-quote
- MZCONFIG_PRINT_GRAPH print-graph

- MZCONFIG_PRINT_STRUCT print-struct
- MZCONFIG_PRINT_BOX print-box
- MZCONFIG_CASE_SENS read-case-sensitive
- MZCONFIG_SQUARE_BRACKETS_ARE_PARENS read-square-brackets-asparens
- MZCONFIG_CURLY_BRACES_ARE_PARENS read-curly-braces-as-parens
- MZCONFIG_ERROR_PRINT_WIDTH error-print-width
- MZCONFIG_ALLOW_SET_UNDEFINED allow-compile-set!-undefined
- MZCONFIG_CUSTODIAN current-custodian
- MZCONFIG_USE_COMPILED_KIND use-compiled-file-paths
- MZCONFIG_LOAD_DIRECTORY current-load-relative-directory
- MZCONFIG_COLLECTION_PATHS current-library-collection-paths
- MZCONFIG_PORT_PRINT_HANDLER global-port-print-handler
- MZCONFIG_LOAD_EXTENSION_HANDLER current-load-extension

To get or set a parameter value for a thread other than the current one, use scheme_get_thread_param and scheme_set_thread_param, each of which takes a Scheme_Thread_Cell_Table to use in resolving or setting a parameter value.

When installing a new parameter with scheme_set_param, no check is performed on the supplied value to ensure that it is a legal value for the parameter; this is the responsibility of the caller of scheme_set_param. Note that Boolean parameters should only be set to the values #t and #f.

New primitive parameter indices are created with scheme_new_param and implemented with scheme_make_parameter and scheme_param_config.

Gets the current value (for the current thread) of the parameter specified by param_id.

Sets the current value (for the current thread) of the parameter specified by *param_id*.

Like scheme_get_param, but using an arbitrary thread's cell-value table.

Like scheme_set_param, but using an arbitrary thread's cell-value table.

Creates and returns a parameterization that extends *base* with a new value *v* (in all threads) for the parameter *param_id*. Use scheme_install_config to make this configuration active in the current thread.

void scheme_install_config(Scheme_Config* config)

Adjusts the current thread's continuation marks to make *config* the current parameterization. Typically, this function is called after scheme_push_continuation_frame to establish a new continuation frame, and then scheme_pop_continuation_frame is called later to remove the frame (and thus the parameterization).

```
Scheme_Thread_Cell_Table*
scheme_inherit_cells(Scheme_Thread_Cell_Table* cells)
```

Creates a new thread-cell-value table, copying values for preserved thread cells from cells.

```
int scheme_new_param()
```

Allocates a new primitive parameter index. This function must be called *before* scheme_basic_env, so it is only available to embedding applications (i.e., not extensions).

Use this function instead of the other primitive-constructing functions, like scheme_make_prim, to create a primitive parameter procedure. See also scheme_param_config, below. This function is only available to embedding applications (i.e., not extensions).

Call this procedure in a primitive parameter procedure to implement the work of getting or setting the parameter. The *name* argument should be the parameter procedure name; it is used to report errors. The *param* argument is a fixnum corresponding to the primitive parameter index returned by scheme_new_param. The *argc* and *argv* arguments should be the un-touched and un-tested arguments that were passed to the primitive parameter. Argument-checking is performed within scheme_param_config using *arity*, *check*, *expected*, and *isbool*:

- If *arity* is non-negative, potential parameter values must be able to accept the specified number of arguments. The *check* and *expected* arguments should be NULL.
- If *check* is not NULL, it is called to check a potential parameter value. The arguments passed to *check* are always 1 and an array that contains the potential parameter value. If *isbool* is 0 and *check* returns scheme_false, then a type error is reported using *name* and *expected*. If *isbool* is 1, then a type error is reported only when *check* returns NULL and any non-NULL return value is used as the actual value to be stored for the parameter.
- Otherwise, *isbool* should be 1. A potential procedure argument is then treated as a Boolean value.

This function is only available to embedding applications (i.e., not extensions).

10 Continuation Marks

A mark can be attached to the current continuation frame using scheme_set_cont_mark. To force the creation of a new frame (e.g., during a nested function call within your function), use scheme_push_continuation_frame, and then remove the frame with scheme_pop_continuation_frame.

void scheme_set_cont_mark(Scheme_Object* key, Scheme_Object* val)

Add/sets a continuation mark in the current continuation.

void scheme_push_continuation_frame(Scheme_Cont_Frame_Data* data)

Creates a new continuation frame. The *data* record need not be initialized, and it can be allocated on the C stack. Supply *data* to scheme_pop_continuation_frame to remove the continuation frame.

void scheme_pop_continuation_frame(Scheme_Cont_Frame_Data* data)

Removes a continuation frame created by scheme_push_continuation_frame.

11 String Encodings

The scheme_utf8_decode function decodes a char array as UTF-8 into either a UCS-4 mzchar array or a UTF-16 short array. The scheme_utf8_encode function encodes either a UCS-4 mzchar array or a UTF-16 short array into a UTF-8 char array.

These functions can be used to check or measure an encoding or decoding without actually producing the result decoding or encoding, and variations of the function provide control over the handling of decoding errors.

Decodes a byte array as UTF-8 to produce either Unicode code points into us (when utf16 is zero) or UTF-16 code units into us cast to short* (when utf16 is non-zero). No nul terminator is added to us.

The result is non-negative when all of the given bytes are decoded, and the result is the length of the decoding (in mzchars or shorts). A -2 result indicates an invalid encoding sequence in the given bytes (possibly because the range to decode ended mid-encoding), and a -3 result indicates that decoding stopped because not enough room was available in the result string.

The *start* and *end* arguments specify a range of s to be decoded. If *end* is negative, strlen(s) is used as the end.

If *us* is NULL, then decoded bytes are not produced, but the result is valid as if decoded bytes were written. The *dstart* and *dend* arguments specify a target range in *us* (in mzchar or short units) for the decoding; a negative value for *dend* indicates that any number of bytes can be written to *us*, which is normally sensible only when *us* is NULL for measuring the length of the decoding.

If *ipos* is non-NULL, it is filled with the first undecoded index within s. If the function result is non-negative, then *ipos is set to the ending index (with is *end* if non-negative, strlen(s) otherwise). If the result is -1 or -2, then *ipos effectively indicates how many bytes were decoded before decoding stopped.

If *permissive* is non-zero, it is used as the decoding of bytes that are not part of a valid UTF-8 encoding. Thus, the function result can be -2 only if *permissive* is 0.

This function does not allocate or trigger garbage collection.

Like scheme_utf8_decode, but the result is always the number of the decoded mzchars or shorts. If a decoding error is encountered, the result is still the size of the decoding up until the error.

Like scheme_utf8_decode, but with fewer arguments. The decoding produces UCS-4 mzchars. If the buffer us is non-NULL, it is assumed to be long enough to hold the decoding (which cannot be longer than the length of the input, though it may be shorter). If *len* is negative, strlen(s) is used as the input length.

Like scheme_utf8_decode, but with fewer arguments. The decoding produces UCS-4 mzchars. If the buffer us must be non-NULL, and it is assumed to be long enough to hold the decoding (which cannot be longer than the length of the input, though it may be shorter). If *len* is negative, strlen(s) is used as the input length.

In addition to the result of scheme_utf8_decode, the result can be -1 to indicate that the input ended with a partial (valid) encoding. A -1 result is possible even when *permissive* is non-zero.

Like scheme_utf8_decode_all with *permissive* as 0, but if *buf* is not large enough (as indicated by *blen*) to hold the result, a new buffer is allocated. Unlike other functions, this one adds a nul terminator to the decoding result. The function result is either *buf* (if it was

big enough) or a buffer allocated with scheme_malloc_atomic.

Like scheme_utf8_decode_to_buffer, but the length of the result (not including the terminator) is placed into *ulen* if *ulen* is non-NULL.

Like scheme_utf8_decode, but without producing the decoded mzchars, and always returning the number of decoded mzchars up until a decoding error (if any). If *might_continue* is non-zero, the a partial valid encoding at the end of the input is not decoded when *permissive* is also non-zero.

If *state* is non-NULL, it holds information about partial encodings; it should be set to zero for an initial call, and then passed back to scheme_utf8_decode along with bytes that extend the given input (i.e., without any unused partial encodings). Typically, this mode makes sense only when *might_continue* and *permissive* are non-zero.

Encodes the given UCS-4 array of mzchars (if *utf16* is zero) or UTF-16 array of shorts (if *utf16* is non-zero) into s. The *end* argument must be no less than *start*.

The array *s* is assumed to be long enough to contain the encoding, but no encoding is written if *s* is NULL. The *dstart* argument indicates a starting place in *s* to hold the encoding. No nul terminator is added to *s*.

The result is the number of bytes produced for the encoding (or that would be produced if *s* was non-NULL). Encoding never fails.

This function does not allocate or trigger garbage collection.

Like scheme_utf8_encode with 0 for *start*, *len* for *end*, 0 for *dstart* and 0 for *utf16*.

Like scheme_utf8_encode_all, but the length of *buf* is given, and if it is not long enough to hold the encoding, a buffer is allocated. A nul terminator is added to the encoded array. The result is either *buf* or an array allocated with scheme_malloc_atomic.

Like scheme_utf8_encode_to_buffer, but the length of the resulting encoding (not including a nul terminator) is reported in *rlen* if it is non-NULL.

Converts a UCS-4 encoding (the indicated range of *text*) to a UTF-16 encoding. The *end* argument must be no less than *start*.

A result buffer is allocated if *buf* is not long enough (as indicated by *bufsize*). If *ulen* is non-NULL, it is filled with the length of the UTF-16 encoding. The *term_size* argument indicates a number of shorts to reserve at the end of the result buffer for a terminator (but no terminator is actually written).

mzchar* scheme_utf16_to_ucs4(const unsigned short* text,

```
int start,
int end,
mzchar* buf,
int bufsize,
intptr_t* ulen,
int term_size)
```

Converts a UTF-16 encoding (the indicated range of *text*) to a UCS-4 encoding. The *end* argument must be no less than *start*.

A result buffer is allocated if *buf* is not long enough (as indicated by *bufsize*). If *ulen* is non-NULL, it is filled with the length of the UCS-4 encoding. The *term_size* argument indicates a number of mzchars to reserve at the end of the result buffer for a terminator (but no terminator is actually written).

12 Bignums, Rationals, and Complex Numbers

Racket supports integers of an arbitrary magnitude; when an integer cannot be represented as a fixnum (i.e., 30 or 62 bits plus a sign bit), then it is represented by the Racket type scheme_bignum_type. There is no overlap in integer values represented by fixnums and bignums.

Rationals are implemented by the type scheme_rational_type, composed of a numerator and a denominator. The numerator and denominator fixnums or bignums (possibly mixed).

Complex numbers are implemented by the types scheme_complex_type and scheme_complex_izi_type, composed of a real and imaginary part. The real and imaginary parts will either be both flonums, both exact numbers (fixnums, bignums, and rationals can be mixed in any way), or one part will be exact 0 and the other part will be a flonum. If the inexact part is inexact 0, the type is scheme_complex_izi_type, otherwise the type is scheme_complex_type; this distinction make it easy to test whether a complex number should be treated as a real number.

int scheme_is_exact(Scheme_Object* n)

Returns 1 if n is an exact number, 0 otherwise (n need not be a number).

int scheme_is_inexact(Scheme_Object* n)

Returns 1 if n is an inexact number, 0 otherwise (n need not be a number).

Scheme_Object* scheme_make_bignum(intptr_t v)

Creates a bignum representing the integer v. This can create a bignum that otherwise fits into a fixnum. This must only be used to create temporary values for use with the bignum functions. Final results can be normalized with scheme_bignum_normalize. Only normalized numbers can be used with procedures that are not specific to bignums.

Scheme_Object* scheme_make_bignum_from_unsigned(uintptr_t v)

Like scheme_make_bignum, but works on unsigned integers.

double scheme_bignum_to_double(Scheme_Object* n)

Converts a bignum to a floating-point number, with reasonable but unspecified accuracy.

float scheme_bignum_to_float(Scheme_Object* n)

If Racket is not compiled with single-precision floats, this procedure is actually a macro alias for scheme_bignum_to_double.

Scheme_Object* scheme_bignum_from_double(double d)

Creates a bignum that is close in magnitude to the floating-point number *d*. The conversion accuracy is reasonable but unspecified.

Scheme_Object* scheme_bignum_from_float(float f)

If Racket is not compiled with single-precision floats, this procedure is actually a macro alias for scheme_bignum_from_double.

Writes a bignum into a newly allocated byte string.

Reads a bignum from a mzchar string, starting from position *offset* in *str*. If the string does not represent an integer, then NULL will be returned. If the string represents a number that fits in 31 bits, then a scheme_integer_type object will be returned.

Like scheme_read_bignum, but from a UTF-8-encoding byte string.

```
Scheme_Object* scheme_bignum_normalize(Scheme_Object* n)
```

If n fits in 31 bits, then a scheme_integer_type object will be returned. Otherwise, n is returned.

```
Scheme_Object* scheme_make_rational(Scheme_Object* n,
Scheme_Object* d)
```

Creates a rational from a numerator and denominator. The n and d parameters must be fixnums or bignums (possibly mixed). The resulting will be normalized (thus, a bignum or fixnum might be returned).

```
double scheme_rational_to_double(Scheme_Object* n)
```

Converts the rational *n* to a double.

float scheme_rational_to_float(Scheme_Object* n)

If Racket is not compiled with single-precision floats, this procedure is actually a macro alias for scheme_rational_to_double.

```
Scheme_Object* scheme_rational_numerator(Scheme_Object* n)
```

Returns the numerator of the rational *n*.

Scheme_Object* scheme_rational_denominator(Scheme_Object* n)

Returns the denominator of the rational *n*.

Scheme_Object* scheme_rational_from_double(double d)

Converts the given double into a maximally-precise rational.

Scheme_Object* scheme_rational_from_float(float d)

If Racket is not compiled with single-precision floats, this procedure is actually a macro alias for scheme_rational_from_double.

Scheme_Object* scheme_make_complex(Scheme_Object* r, Scheme_Object* i)

Creates a complex number from real and imaginary parts. The r and i arguments must be fixnums, bignums, flonums, or rationals (possibly mixed). The resulting number will be normalized (thus, a real number might be returned).

Scheme_Object* scheme_complex_real_part(Scheme_Object* n)

Returns the real part of the complex number *n*.

Scheme_Object* scheme_complex_imaginary_part(Scheme_Object* n)

Returns the imaginary part of the complex number *n*.

13 Ports and the Filesystem

Ports are represented as Racket values with the types scheme_input_port_type and scheme_output_port_type. The function scheme_read takes an input port value and returns the next S-expression from the port. The function scheme_write takes an output port and a value and writes the value to the port. Other standard low-level port functions are also provided, such as scheme_getc.

File ports are created with scheme_make_file_input_port and scheme_make_file_output_port; these functions take a FILE * file pointer and return a Scheme port. Strings are read or written with scheme_make_byte_string_input_port, which takes a nul-terminated byte string, and scheme_make_byte_string_output_port, which takes no arguments. The contents of a string output port are obtained with scheme_get_byte_string_output.

Custom ports, with arbitrary read/write handlers, are created with scheme_make_input_port and scheme_make_output_port.

When opening a file for any reason using a name provided from Racket, use scheme_expand_filename to normalize the filename and resolve relative paths.

Scheme_Object* scheme_read(Scheme_Object* *port*)

reads the next S-expression from the given input port.

writes the Scheme value *obj* to the given output port.

Like scheme_write, but the printing is truncated to n bytes. (If printing is truncated, the last bytes are printed as ".".)

displays the Racket value *obj* to the given output port.

Like scheme_display, but the printing is truncated to *n* bytes. (If printing is truncated, the last three bytes are printed as ".".)

Writes len bytes of str to the given output port.

Writes *len* characters of *str* to the given output port.

Writes *len* bytes of *str*, starting with the *d*th character. Bytes are written to the given output port, and errors are reported as from *who*.

If *rarely_block* is 0, the write blocks until all *len* bytes are written, possibly to an internal buffer. If *rarely_block* is 2, the write never blocks, and written bytes are not buffered. If *rarely_block* is 1, the write blocks only until at least one byte is written (without buffering) or until part of an internal buffer is flushed.

Supplying 0 for *len* corresponds to a buffer-flush request. If *rarely_block* is 2, the flush request is non-blocking, and if *rarely_block* is 0, it is blocking. (A *rarely_block* of 1 is the same as 0 in this case.)

The result is -1 if no bytes are written from *str* and unflushed bytes remain in the internal buffer. Otherwise, the return value is the number of written characters.

Like scheme_put_byte_string, but for a mzchar string, and without the non-blocking option.

Prints the Racket value *obj* using write to a newly allocated string. If *len* is not NULL, **len* is set to the length of the bytes string.

Like scheme_write_to_string, but the string is truncated to n bytes. (If the string is truncated, the last three bytes are ".".)

Prints the Racket value *obj* using display to a newly allocated string. If *len* is not NULL, **len* is set to the length of the string.

Like scheme_display_to_string, but the string is truncated to *n* bytes. (If the string is truncated, the last three bytes are ".".)

```
void scheme_debug_print(Scheme_Object* obj)
```

Prints the Racket value obj using write to the main thread's output port.

```
void scheme_flush_output(Scheme_Object* port)
```

If *port* is a file port, a buffered data is written to the file. Otherwise, there is no effect. *port* must be an output port.

```
int scheme_get_byte(Scheme_Object* port)
```

Get the next byte from the given input port. The result can be EOF.

```
int scheme_getc(Scheme_Object* port)
```

Get the next character from the given input port (by decoding bytes as UTF-8). The result can be EOF.

```
int scheme_peek_byte(Scheme_Object* port)
```

Peeks the next byte from the given input port. The result can be EOF.

```
int scheme_peekc(Scheme_Object* port)
```

Peeks the next character from the given input port (by decoding bytes as UTF-8). The result can be EOF.

Like scheme_peek_byte, but with a skip count. The result can be EOF.

Like scheme_peekc, but with a skip count. The result can be EOF.

Gets multiple bytes at once from a port, reporting errors with the name *who*. The *size* argument indicates the number of requested bytes, to be put into the *buffer* array starting at *offset*. The return value is the number of bytes actually read, or EOF if an end-of-file is encountered without reading any bytes.

If *only_avail* is 0, then the function blocks until *size* bytes are read or an end-of-file is reached. If *only_avail* is 1, the function blocks only until at least one byte is read. If *only_avail* is 2, the function never blocks. If *only_avail* is -1, the function blocks only until at least one byte is read but also allows breaks (with the guarantee that bytes are read or a break is raised, but not both).

If *peek* is non-zero, then the port is peeked instead of read. The *peek_skip* argument indicates a portion of the input stream to skip as a non-negative, exact integer (fixnum or bignum). In this case, an *only_avail* value of 1 means to continue the skip until at least one byte can be returned, even if it means multiple blocking reads to skip bytes.

If *peek* is zero, then *peek_skip* should be either NULL (which means zero) or the fixnum zero.

Like scheme_get_byte_string, but for characters (by decoding bytes as UTF-8), and without the non-blocking option.

For backward compatibility: calls scheme_get_byte_string in essentially the obvious way with *only_avail* as 0; if *size* is negative, then it reads *-size* bytes with *only_avail* as 1.

Puts the byte *ch* back as the next character to be read from the given input port. The character need not have been read from *port*, and scheme_ungetc can be called to insert up to five characters at the start of *port*.

Use scheme_get_byte followed by scheme_ungetc only when your program will certainly call scheme_get_byte again to consume the byte. Otherwise, use scheme_peek_byte, because some a port may implement peeking and getting differently.

int scheme_byte_ready(Scheme_Object* port)

Returns 1 if a call to scheme_get_byte is guaranteed not to block for the given input port.

int scheme_char_ready(Scheme_Object* port)

Returns 1 if a call to scheme_getc is guaranteed not to block for the given input port.

Requests that appropriate bits are set in *fds* to specify which file descriptors(s) the given input port reads from. (*fds* is sort a pointer to an fd_set struct; see §8.4.1 "Callbacks for Blocked Threads".)

```
intptr_t scheme_tell(Scheme_Object* port)
```

Returns the current read position of the given input port, or the current file position of the given output port.

intptr_t scheme_tell_line(Scheme_Object* port)

Returns the current read line of the given input port. If lines are not counted, -1 is returned.

```
void scheme_count_lines(Scheme_Object* port)
```

Turns on line-counting for the given input port. To get accurate line counts, call this function immediately after creating a port.

Sets the file position of the given input or output port (from the start of the file). If the port does not support position setting, an exception is raised.

void scheme_close_input_port(Scheme_Object* port)

Closes the given input port.

void scheme_close_output_port(Scheme_Object* port)

Closes the given output port.

Fills **fd* with a file-descriptor value for *port* if one is available (i.e., the port is a file-stream port and it is not closed). The result is non-zero if the file-descriptor value is available, zero otherwise. On Windows, a "file dscriptor" is a file HANDLE.

```
intptr_t scheme_get_port_fd(Scheme_Object* port)
```

Like scheme_get_port_file_descriptor, but a file descriptor or HANDLE is returned directly, and the result is -1 if no file descriptor or HANDLE is available.

Fills **s* with a socket value for *port* if one is available (i.e., the port is a TCP port and it is not closed). The result is non-zero if the socket value is available, zero otherwise. On Windows, a socket value has type SOCKET.

Scheme_Object* scheme_make_port_type(char* *name*)

Creates a new port subtype.

Creates a new input port with arbitrary control functions. The *subtype* is an arbitrary value to distinguish the port's class. The pointer *data* will be installed as the port's user data, which

can be extracted/set with the SCHEME_INPORT_VAL macro. The *name* object is used as the port's name (for object-name and as the default source name for read-syntax).

If *must_close* is non-zero, the new port will be registered with the current custodian, and *close_fun* is guaranteed to be called before the port is garbage-collected.

Although the return type of scheme_make_input_port is Scheme_Input_Port*, it can be cast into a Scheme_Object*.

The functions are as follows.

Reads bytes into *buffer*, starting from *offset*, up to *size* bytes (i.e., *buffer* is at least *offset* plus *size* long). If *nonblock* is 0, then the function can block indefinitely, but it should return when at least one byte of data is available. If *nonblock* is 1, the function should never block. If *nonblock* is 2, a port in unbuffered mode should return only bytes previously forced to be buffered; other ports should treat a *nonblock* of 2 like 1. If *nonblock* is -1, the function can block, but should enable breaks while blocking. The function should return 0 if no bytes are ready in non-blocking mode. It should return EOF if an end-of-file is reached (and no bytes were read into *buffer*). Otherwise, the function should return the number of read bytes. The function can raise an exception to report an error.

The *unless* argument will be non-NULL only when *nonblocking* is non-zero (except as noted below), and only if the port supports progress events. If *unless* is non-NULL and SCHEME_CDR(*unless*) is non-NULL, the latter is a progress event specific to the port. The *get_bytes_fun* function should return SCHEME_UNLESS_READY instead of reading bytes if the event in *unless* becomes ready before bytes can be read. In particular, *get_bytes_fun* should check the event in *unless* before taking any action, and it should check the event in *unless* after any operation that may allow Racket thread swaps. If the read must block, then it should unblock if the event in *unless* becomes ready.

If scheme_progress_evt_via_get is used for *progress_evt_fun*, then *unless* can be non-NULL even when *nonblocking* is 0. In all modes, *get_bytes_fun* must call scheme_unless_ready to check *unless_evt*. Furthermore, after any potentially thread-swapping operation, *get_bytes_fun* must call scheme_wait_input_allowed, because another thread may be attempting to commit, and *unless_evt* must be checked after scheme_wait_input_allowed returns. To block, the port should use scheme_block_until_unless instead of scheme_block_until. Finally, in blocking mode, *get_bytes_fun* must re-

turn after immediately reading data, without allowing a Racket thread swap.

Can be NULL to use a default implementation of peeking that uses *get_bytes_fun*. Otherwise, the protocol is the same as for *get_bytes_fun*, except that an extra *skip* argument indicates the number of input elements to skip (but *skip* does not apply to *buffer*). The *skip* value will be a non-negative exact integer, either a fixnum or a bignum.

Scheme_Object* progress_evt_fun(Scheme_Input_Port* port)

Called to obtain a progress event for the port, such as for port-progressevt. This function can be NULL if the port does not support progress events. Use scheme_progress_evt_via_get to obtain a default implementation, in which case peeked_read_fun should be scheme_peeked_read_via_get, and get_bytes_fun and peek_bytes_fun should handle unless as described above.

> Called to commit previously peeked bytes, just like the sixth argument to make-input-port. Use scheme_peeked_read_via_get for the default implementation of commits when *progress_evt_fun* is scheme_progress_evt_via_get.

> The *peeked_read_fun* function must call scheme_port_count_lines on a successful commit to adjust the port's position. If line counting is enabled for the port and if line counting uses the default implementation, *peeked_read_fun* should supply a non-NULL byte-string argument to scheme_port_count_lines, so that character and line counts can be tracked correctly.

int char_ready_fun(Scheme_Input_Port* port)

Returns 1 when a non-blocking get_bytes_fun will return bytes or an EOF.

void close_fun(Scheme_Input_Port* port)

Called to close the port. The port is not considered closed until the function returns.

Called when the port is blocked on a read; *need_wakeup_fun* should set appropriate bits in *fds* to specify which file descriptor(s) it is blocked on. The *fds* argument is conceptually an array of three fd_set structs (one for read, one for write, one for exceptions), but manipulate this array using scheme_get_fdset to get a particular element of the array, and use MZ_FD_XXX instead of FD_XXX to manipulate a single "fd_set". On Windows, the first "fd_set" can also contain OS-level semaphores or other handles via scheme_add_fd_handle.

```
Scheme_Output_Port*
```

```
scheme_make_output_port(Scheme_Object* subtype,
```

void* data, Scheme_Object* name, Scheme_Write_String_Evt_Fun write_bytes_evt_fun, Scheme_Write_String_Fun write_bytes_fun, Scheme_Out_Ready_Fun char_ready_fun, Scheme_Close_Output_Fun close_fun, Scheme_Need_Wakeup_Output_Fun need_wakeup_fun, Scheme_Write_Special_Evt_Fun write_special_evt_fun, Scheme_Write_Special_Fun write_special_fun, int must_close)

Creates a new output port with arbitrary control functions. The *subtype* is an arbitrary value to distinguish the port's class. The pointer *data* will be installed as the port's user data, which can be extracted/set with the SCHEME_OUTPORT_VAL macro. The *name* object is used as the port's name.

If *must_close* is non-zero, the new port will be registered with the current custodian, and *close_fun* is guaranteed to be called before the port is garbage-collected.

Although the return type of scheme_make_output_port is Scheme_Output_Port*, it can be cast into a Scheme_Object*.

The functions are as follows.

Returns an event that writes up to *size* bytes atomically when event is chosen in a synchronization. Supply NULL if bytes cannot be written atomically, or supply scheme_write_evt_via_write to use the default implementation in terms of write_bytes_fun (with *rarely_block* as 2).

Write bytes from *buffer*, starting from *offset*, up to *size* bytes (i.e., *buffer* is at least *offset* plus *size* long). If *rarely_block* is 0, then the function can block indefinitely, and it can buffer output. If *rarely_block* is 2, the function should never block, and it should not buffer output. If *rarely_block* is 1, the function should not buffer data, and it should block only until writing at least one byte, either from *buffer* or an internal buffer. The function should return the number of bytes from *buffer* that were written; when *rarely_block* is non-zero and bytes remain in an internal buffer, it should return -1. The *size* argument can be 0 when *rarely_block* is 0 for a blocking flush, and it can be 0 if *rarely_block* is 2 for a non-blocking flush. If *enable_break* is true, then it should enable breaks while blocking. The function can raise an exception to report an error.

int char_ready_fun(Scheme_Output_Port* port)

Returns 1 when a non-blocking *write_bytes_fun* will write at least one byte or flush at least one byte from the port's internal buffer.

void close_fun(Scheme_Output_Port* port)

Called to close the port. The port is not considered closed until the function returns. This function is allowed to block (usually to flush a buffer) unless scheme_close_should_force_port_closed returns a non-zero result, in which case the function must return without blocking.

Called when the port is blocked on a write; *need_wakeup_fun* should set appropriate bits in *fds* to specify which file descriptor(s) it is blocked on. The *fds* argument is conceptually an array of three fd_set structs (one for read, one for write, one for exceptions), but manipulate this array using scheme_get_fdset to get a particular element of the array, and use MZ_FD_XXX instead of FD_XXX to manipulate a single "fd_set". On Windows, the first "fd_set" can also contain OS-level semaphores or other handles via scheme_add_fd_handle.

Returns an event that writes *v* atomically when event is chosen in a synchronization. Supply NULL if specials cannot be written atomically (or at all), or supply scheme_write_special_evt_via_write_special to use the default implementation in terms of write_special_fun (with *non_block* as 1).

Called to write the special value v for write-special (when *non_block* is 0) or write-special-avail* (when *non_block* is 1). If NULL is supplied instead of a function pointer, then write-special and write-special-avail* produce an error for this port.

Sets the implementation of port-next-location for *port*, which is used when line counting is enabled for *port*.

```
Scheme_Object* location_fun(Scheme_Port* port)
```

Returns three values: a positive exact integer or #f for a line number, a nonnegative exact integer or #f for a column (which must be #f if and only if the line number is #f), and a positive exact integer or #f for a character position.

Installs a notification callback that is invoked if line counting is subsequently enabled for *port*.

void count_lines_fun(Scheme_Port* port)

Updates the position of *port* as reported by file-position as well as the locations reported by port-next-location when the default implement of character and line counting is used. This function is intended for use by a peek-commit implementation in an input port.

The *got* argument indicates the number of bytes read from or written to *port*. The *buffer* argument is used only when line counting is enabled, and it represents specific bytes read or written for the purposes of character and line counting. The *buffer* argument can be NULL, in which case *got* non-newline characters are assumed. The *offset* argument indicates a starting offset into *buffer*, so "buffer" must be at least *offset* plus *got* bytes long.

Scheme_Object* scheme_make_file_input_port(FILE* fp)

Creates a Scheme input file port from an ANSI C file pointer. The file must never block on reads.

Opens *filename* for reading. In an exception is raised, the exception message uses *who* as the name of procedure that raised the exception.

Creates a Racket input file port from an ANSI C file pointer. The file must never block on reads. The *name* argument is used as the port's name.

Opens *filename* for writing in 'truncate/replace mode. If an exception is raised, the exception message uses *who* as the name of procedure that raised the exception.

Scheme_Object* scheme_make_file_output_port(FILE* *fp*)

Creates a Racket output file port from an ANSI C file pointer. The file must never block on writes.

Creates a Racket input port for a file descriptor *fd*. On Windows, *fd* can be a HANDLE for a stream, and it should never be a file descriptor from the C library or a WinSock socket.

The *name* object is used for the port's name. Specify a non-zero value for *regfile* only if the file descriptor corresponds to a regular file (which implies that reading never blocks, for example).

On Windows, *win_textmode* can be non-zero to make trigger auto-conversion (at the byte level) of CRLF combinations to LF.

Closing the resulting port closes the file descriptor.

Instead of calling both scheme_make_fd_input_port and scheme_make_fd_output_port on the same file descriptor, call scheme_make_fd_output_port with a non-zero last argument. Otherwise, closing

one of the ports causes the file descriptor used by the other to be closed as well.

Creates a Racket output port for a file descriptor *fd*. On Windows, *fd* can be a HANDLE for a stream, and it should never be a file descriptor from the C library or a WinSock socket.

The *name* object is used for the port's name. Specify a non-zero value for *regfile* only if the file descriptor corresponds to a regular file (which implies that reading never blocks, for example).

On Windows, *win_textmode* can be non-zero to make trigger auto-conversion (at the byte level) of CRLF combinations to LF.

Closing the resulting port closes the file descriptor.

If $read_too$ is non-zero, the function produces multiple values (see §6.3 "Multiple Values") instead of a single port. The first result is an input port for fd, and the second is an output port for fd. These ports are connected in that the file descriptor is closed only when both of the ports are closed.

Creates Racket input and output ports for a TCP socket *s*. The *name* argument supplies the name for the ports. If *close* is non-zero, then the ports assume responsibility for closing the socket. The resulting ports are written to *inp* and *outp*.

Scheme_Object* scheme_make_byte_string_input_port(char* str)

Creates a Racket input port from a byte string; successive read-chars on the port return successive bytes in the string.

Scheme_Object* scheme_make_byte_string_output_port()

Creates a Racket output port; all writes to the port are kept in a byte string, which can be obtained with scheme_get_byte_string_output.

char* scheme_get_byte_string_output(Scheme_Object* port)

Returns (in a newly allocated byte string) all data that has been written to the given string output port so far. (The returned string is nul-terminated.)

Returns (in a newly allocated byte string) all data that has been written to the given string output port so far and fills in *len with the length of the string in bytes (not including the nul terminator).

Creates a pair of ports, setting **read* and **write*; data written to **write* can be read back out of **read*. The pipe can store arbitrarily many unread characters,

Like scheme_pipe if *limit* is 0. If *limit* is positive, creates a pipe that stores at most *limit* unread characters, blocking writes when the pipe is full.

```
Scheme_Input_Port* scheme_input_port_record(Scheme_Object* port)
```

Returns the input-port record for *port*, which may be either a raw-port object with type scheme_input_port_type or a structure with the prop:input-port property.

```
Scheme_Output_Port*
scheme_output_port_record(Scheme_Object* port)
```

Returns the output-port record for *port*, which may be either a raw-port object with type scheme_output_port_type or a structure with the prop:output-port property.

```
int scheme_file_exists(char* name)
```

Returns 1 if a file by the given name exists, 0 otherwise. If *name* specifies a directory, FALSE is returned. The *name* should be already expanded.

int scheme_directory_exists(char* name)

Returns 1 if a directory by the given name exists, 0 otherwise. The *name* should be already expanded.

Cleanses the pathname name (see cleanse-path) and resolves relative paths with respect

to the current directory parameter. The *len* argument is the length of the input string; if it is -1, the string is assumed to be null-terminated. The *where* argument is used to raise an exception if there is an error in the filename; if this is NULL, an error is not reported and NULL is returned instead. If *expanded* is not NULL, **expanded* is set to 1 if some expansion takes place, or 0 if the input name is simply returned.

If guards is not 0, then scheme_security_check_file (see §15 "Security Guards") is called with *name*, *where*, and *checks* (which implies that *where* should never be NULL unless guards is 0). Normally, guards should be SCHEME_GUARD_FILE_EXISTS at a minimum. Note that a failed access check will result in an exception.

Like scheme_expand_string, but given a *name* that can be a character string or a path value.

Scheme_Object* scheme_char_string_to_path(Scheme_Object* s)

Converts a Racket character string into a Racket path value.

Scheme_Object* scheme_path_to_char_string(Scheme_Object* s)

Converts a Racket path value into a Racket character string.

Scheme_Object* scheme_make_path(char* bytes)

Makes a path value given a byte string. The bytes string is copied.

Scheme_Object* scheme_make_path_without_copying(char* bytes)

Like scheme_make_path, but the string is not copied.

Makes a path whose byte form has size *len*. A copy of *bytes* is made if *copy* is not 0. The string *bytes* should contain *len* bytes, and if *copy* is zero, *bytes* must have a nul terminator in addition. If *len* is negative, then the nul-terminated length of *bytes* is used for the length.

Like scheme_make_sized_path, except the *len* bytes start from position *d* in *bytes*. If *d* is

non-zero, then copy must be non-zero.

Mac OS X only: Converts an FSSpec record (defined by Mac OS X) into a pathname string. If *spec* contains only directory information (via the vRefNum and parID fields), *isdir* should be 1, otherwise it should be 0.

Mac OS X only: Converts a pathname into an FSSpec record (defined by Mac OS X), returning 1 if successful and 0 otherwise. If *type* is not NULL and *filename* is a file that exists, *type* is filled with the file's four-character Mac OS X type. If *type* is not NULL and *filename* is not a file that exists, *type* is filled with 0.

Gets the current working directory according to the operating system. This is separate from Racket's current directory parameter.

The directory path is written into *buf*, of length *buflen*, if it fits. Otherwise, a new (collectable) string is allocated for the directory path. If *actlen* is not NULL, **actlen* is set to the length of the current directory path. If *noexn* is no 0, then an exception is raised if the operation fails.

Sets the current working directory according to the operating system. This is separate from Racket's current directory parameter.

If noexn is not 0, then an exception is raised if the operation fails.

Creates a string like Racket's format procedure, using the format string *format* (of length *flen*) and the extra arguments specified in *argc* and *argv*. If *rlen* is not NULL, **rlen* is filled with the length of the resulting string.

Writes to the current output port like Racket's printf procedure, using the format string *format* (of length *flen*) and the extra arguments specified in *argc* and *argv*.

Like scheme_format, but takes a UTF-8-encoding byte string.

Like scheme_printf, but takes a UTF-8-encoding byte string.

```
int scheme_close_should_force_port_closed()
```

This function must be called by the close function for a port created with scheme_make_output_port.

14 Structures

A new Racket structure type is created with scheme_make_struct_type. This creates the structure type, but does not generate the constructor, etc. procedures. The scheme_make_struct_values function takes a structure type and creates these procedures. The scheme_make_struct_names function generates the standard structure procedures names given the structure type's name. Instances of a structure type are created with scheme_make_struct_instance and the function scheme_is_struct_instance tests a structure's type. The scheme_struct_ref and scheme_struct_set functions access or modify a field of a structure.

The structure procedure values and names generated by scheme_make_struct_values and scheme_make_struct_names can be restricted by passing any combination of these flags:

- SCHEME_STRUCT_NO_TYPE the structure type value/name is not returned.
- SCHEME_STRUCT_NO_CONSTR the constructor procedure value/name is not returned.
- SCHEME_STRUCT_NO_PRED— the predicate procedure value/name is not returned.
- SCHEME_STRUCT_NO_GET the selector procedure values/names are not returned.
- SCHEME_STRUCT_NO_SET the mutator procedure values/names are not returned.
- SCHEME_STRUCT_GEN_GET the field-independent selector procedure value/name is returned.
- SCHEME_STRUCT_GEN_SET the field-independent mutator procedure value/name is returned.
- SCHEME_STRUCT_NO_MAKE_PREFIX the constructor name omits a make- prefix, like struct instead of define-struct.

When all values or names are returned, they are returned as an array with the following order: structure type, constructor, predicate, first selector, first mutator, second selector, etc., field-independent select, field-independent mutator. When particular values/names are omitted, the array is compressed accordingly.

Creates and returns a new structure type. The *base_name* argument is used as the name of the new structure type; it must be a symbol. The *super_type* argument should be NULL or an existing structure type to use as the super-type. The *inspector* argument should be NULL or an inspector to manage the type. The *num_init_fields* argument specifies the number of fields for instances of this structure type that have corresponding constructor arguments. (If a super-type is used, this is the number of additional fields, rather than the total number.) The *num_auto_fields* argument specifies the number of additional fields that have no corresponding constructor arguments, and they are initialized to *auto_val*. The *properties* argument is a list of property-value pairs. The *guard* argument is either NULL or a procedure to use as a constructor guard.

Creates and returns an array of standard structure value name symbols. The *base_name* argument is used as the name of the structure type; it should be the same symbol passed to the associated call to scheme_make_struct_type. The *field_names* argument is a (Racket) list of field name symbols. The *flags* argument specifies which names should be generated, and if *count_out* is not NULL, *count_out* is filled with the number of names returned in the array.

Creates and returns an array of the standard structure value and procedure values for *struct_type*. The *struct_type* argument must be a structure type value created by scheme_make_struct_type. The *names* procedure must be an array of name symbols, generally the array returned by scheme_make_struct_names. The *count* argument specifies the length of the *names* array (and therefore the number of expected return values) and the *flags* argument specifies which values should be generated.

Creates an instance of the structure type *struct_type*. The *argc* and *argv* arguments provide the field values for the new instance.

Returns 1 if v is an instance of *struct_type* or 0 otherwise.

Returns the *n*th field (counting from 0) in the structure *s*.

Sets the *n*th field (counting from 0) in the structure s to v.

15 Security Guards

Before a primitive procedure accesses the filesystem or creates a network connection, it should first consult the current security guard to determine whether such access is allowed for the current thread.

File access is normally preceded by a call to scheme_expand_filename, which accepts flags to indicate the kind of filesystem access needed, so that the security guard is consulted automatically.

An explicit filesystem-access check can be made by calling scheme_security_check_file. Similarly, an explicit network-access check is performed by calling scheme_security_check_network.

Consults the current security manager to determine whether access is allowed to *filename*. The *guards* argument should be a bitwise combination of the following:

- SCHEME_GUARD_FILE_READ
- SCHEME_GUARD_FILE_WRITE
- SCHEME_GUARD_FILE_EXECUTE
- SCHEME_GUARD_FILE_DELETE
- SCHEME_GUARD_FILE_EXISTS (do not combine with other values)

The *filename* argument can be NULL (in which case #f is sent to the security manager's procedure), and *guards* should be SCHEME_GUARD_FILE_EXISTS in that case.

If access is denied, an exception is raised.

Consults the current security manager to determine whether access is allowed for creating a client connection to *host* on port number *portno*. If *host* is NULL, the security manager is consulted for creating a server at port number *portno*.

If access is denied, an exception is raised.

16 Custodians

When an extension allocates resources that must be explicitly freed (in the same way that a port must be explicitly closed), a Racket object associated with the resource should be placed into the management of the current custodian with scheme_add_managed.

Before allocating the resource, call scheme_custodian_check_available to ensure that the relevant custodian is not already shut down. If it is, scheme_custodian_check_available will raise an exception. If the custodian is shut down when scheme_add_managed is called, the close function provided to scheme_add_managed will be called immediately, and no exception will be reported.

```
Scheme_Custodian* scheme_make_custodian(Scheme_Custodian* m)
```

Creates a new custodian as a subordinate of m. If m is NULL, then the main custodian is used as the new custodian's supervisor. Do not use NULL for m unless you intend to create an especially privileged custodian.

Places the value o into the management of the custodian m. If m is NULL, the current custodian is used.

The f function is called by the custodian if it is ever asked to "shutdown" its values; o and *data* are passed on to f, which has the type

If *strong* is non-zero, then the newly managed value will be remembered until either the custodian shuts it down or scheme_remove_managed is called. If *strong* is zero, the value is allowed to be garbage collected (and automatically removed from the custodian).

Independent of whether *strong* is zero, the value *o* is initially weakly held. A value associated with a custodian can therefore be finalized via will executors.

The return value from scheme_add_managed can be used to refer to the value's custodian later in a call to scheme_remove_managed. A value can be registered with at most one custodian.

If m (or the current custodian if m is NULL) is shut down, then f is called immediately, and the result is NULL.

Like scheme_add_managed with a 1 final argument, but also causes f to be called when Racket exists without an explicit custodian shutdown.

Checks whether *m* is already shut down, and raises an error if so. If *m* is NULL, the current custodian is used. The *name* argument is used for error reporting. The *resname* argument will likely be used for checking pre-set limits in the future; pre-set limits will have symbolic names, and the *resname* string will be compared to the symbols.

Removes *o* from the management of its custodian. The *mref* argument must be a value returned by scheme_add_managed or NULL.

void scheme_close_managed(Scheme_Custodian* m)

Instructs the custodian *m* to shutdown all of its managed values.

void scheme_add_atexit_closer(Scheme_Exit_Closer_Func f)

Installs a function to be called on each custodian-registered item and its closer when Racket is about to exit. The registered function has the type

where d is the second argument for f.

At-exit functions are run in reverse of the order that they are added. An at-exit function is initially registered (and therefore runs last) that flushes each file-stream output port and calls every function registered with scheme_add_managed_close_on_exit.

An at-exit function should not necessarily apply the closer function for every object that it is given. In particular, shutting down a file-stream output port would disable the flushing action of the final at-exit function. Typically, an at-exit function ignores most objects while handling a specific type of object that requires a specific clean-up action before the OS-level process terminates.

17 Subprocesses

On Unix and Mac OS X, subprocess handling involves fork, waitpid, and SIGCHLD, which creates a variety of issues within an embedding application. On Windows, subprocess handling is more straightforward, since no fork is required, and since Windows provides an abstraction that is a close fit to Racket's subprocess values.

After Racket creates a subprocess via subprocess (or system, process, etc.), it periodically polls the process status using waitpid. If the process is created as its own group, then the call to waitpid uses the created subprocess's process ID; for all other subprocesses, polling uses a single call to waitpid with the first argument as 0. Using 0, in particular, can interfere with other libraries in an embedding context, so Racket refrains from calling waitpid if no subprocesses are pending.

Racket may or may not rely on a SIGCHLD handler, and it may or may not block SIGCHLD. Currently, when Racket is compiled to support places, Racket blocks SIGCHLD on start up with the expectation that all created threads have SIGCHLD blocked. When Racket is not compiled to support places, then a SIGCHLD handler is installed.

Using fork in an application that embeds Racket is problematic for several reasons: Racket may install a SIGALRM handler and schedule alarms to implement context switches, it may have file descriptors open that should be closed in a child process, and it may have changed the disposition of signals such as SIGCHLD. Consequently, embedding Racket in a process that forks is technically not supported; in the future, Racket may provide better support for such applications.

18 Miscellaneous Utilities

The MZSCHEME_VERSION preprocessor macro is defined as a string describing the version of Racket. The MZSCHEME_VERSION_MAJOR and MZSCHEME_VERSION_MINOR macros are defined as the major and minor version numbers, respectively.

```
Returns 1 if the Scheme values are eq?.
```

Returns 1 if the Scheme values are eqv?.

Returns 1 if the Scheme values are equal?.

Like scheme_equal, but accepts an extra value for cycle tracking. This procedure is meant to be called by a procedure installed with scheme_set_type_equality.

intptr_t scheme_equal_hash_key(Scheme_Object* obj)

Returns the primary equal?-hash key for obj.

intptr_t scheme_equal_hash_key2(Scheme_Object* obj)

Returns the secondary equal?-hash key for obj.

Like scheme_equal_hash_key, but accepts an extra value for cycle tracking. This procedure is meant to be called by a hashing procedure installed with scheme_set_type_equality.

Like scheme_equal_hash_key2, but accepts an extra value for cycle tracking. This procedure is meant to be called by a secondary hashing procedure installed with scheme_set_type_equality.

Creates and returns a list of length c with the elements elems.

int scheme_list_length(Scheme_Object* list)

Returns the length of the list. If *list* is not a proper list, then the last cdr counts as an item. If there is a cycle in *list* (involving only cdrs), this procedure will not terminate.

int scheme_proper_list_length(Scheme_Object* list)

Returns the length of the list, or -1 if it is not a proper list. If there is a cycle in *list* (involving only cdrs), this procedure returns -1.

Scheme_Object* scheme_car(Scheme_Object* pair)

Returns the car of the pair.

Scheme_Object* scheme_cdr(Scheme_Object* pair)

Returns the cdr of the pair.

Scheme_Object* scheme_cadr(Scheme_Object* pair)

Returns the cadr of the pair.

Scheme_Object* scheme_caddr(Scheme_Object* pair)

Returns the caddr of the pair.

Scheme_Object* scheme_vector_to_list(Scheme_Object* vec)

Creates a list with the same elements as the given vector.

Scheme_Object* scheme_list_to_vector(Scheme_Object* list)

Creates a vector with the same elements as the given list.

Scheme_Object* scheme_append(Scheme_Object* *lstx*, Scheme_Object* *lsty*)

Non-destructively appends the given lists.

Scheme_Object* scheme_unbox(Scheme_Object* *obj*)

Returns the contents of the given box.

 Sets the contents of the given box.

The same as dynamic-require. The *argc* argument must be 2, and *argv* contains the arguments.

```
Scheme_Object*
scheme_namespace_require(Scheme_Object* prim_req_spec)
```

The same as namespace-require.

```
Scheme_Object* scheme_load(char* file)
```

Loads the specified Racket file, returning the value of the last expression loaded, or NULL if the load fails.

Scheme_Object* scheme_load_extension(char* *filename*)

Loads the specified Racket extension file, returning the value provided by the extension's initialization function.

```
Scheme_Hash_Table* scheme_make_hash_table(int type)
```

Creates a hash table. The *type* argument must be either SCHEME_hash_ptr or SCHEME_hash_string, which determines how keys are compared (unless the hash and compare functions are modified in the hash table record; see below). A SCHEME_hash_ptr table hashes on a key's pointer address, while SCHEME_hash_string uses a key as a char* and hashes on the null-terminated string content. Since a hash table created with SCHEME_hash_string (instead of SCHEME_hash_ptr) does not use a key as a Racket value, it cannot be used from Racket code.

Although the hash table interface uses the type Scheme_Object* for both keys and values, the table functions never inspect values, and they inspect keys only for SCHEME_hash_string hashing. Thus, the actual types of the values (and keys, for SCHEME_hash_ptr tables) can be anything.

The public portion of the Scheme_Hash_Table type is defined roughly as follows:

```
typedef struct Scheme_Hash_Table {
   Scheme_Object so; /* so.type == scheme_hash_table_type */
   /* ... */
   int size; /* size of keys and vals arrays */
   int count; /* number of mapped keys */
   Scheme_Object **keys;
   Scheme_Object **vals;
   void (*make_hash_indices)(void *v, intptr_t *h1, intptr_t *h2);
   int (*compare)(void *v1, void *v2);
```

/* ... */
} Scheme_Hash_Table;

The make_hash_indices and compare function pointers can be set to arbitrary hashing and comparison functions (before any mapping is installed into the table). A hash function should fill h1 with a primary hash value and h2 with a secondary hash value; the values are for double-hashing, where the caller takes appropriate modulos. Either h1 or h2 can be NULL if the corresponding hash code is not needed.

To traverse the hash table content, iterate over *keys* and *vals* in parallel from 0 to size-1, and ignore *keys* where the corresponding *vals* entry is NULL. The count field indicates the number of non-NULL values that will be encountered.

Scheme_Hash_Table* scheme_make_hash_table_equal()

Like scheme_make_hash_table, except that keys are treated as Racket values and hashed based on equal? instead of eq?.

Sets the current value for key in table to val. If val is NULL, the key is unmapped in table.

Returns the current value for key in table, or NULL if key has no value.

Like make_hash_table, but bucket tables are somewhat more flexible, in that hash buckets are accessible and weak keys are supported. (They also consume more space than hash tables.)

The *type* argument must be either SCHEME_hash_ptr, SCHEME_hash_string, or SCHEME_hash_weak_ptr. The first two are the same as for hash tables. The last is like SCHEME_hash_ptr, but the keys are weakly held.

The public portion of the Scheme_Bucket_Table type is defined roughly as follows:

```
typedef struct Scheme_Bucket_Table {
   Scheme_Object so; /* so.type == scheme_variable_type */
   /* ... */
   int size; /* size of buckets array */
   int count; /* number of buckets, >= number of mapped keys */
   Scheme_Bucket **buckets;
```

```
void (*make_hash_indices)(void *v, intptr_t *h1, intptr_t *h2);
int (*compare)(void *v1, void *v2);
/* ... */
} Scheme_Bucket_Table;
```

The make_hash_indices and compare functions are used as for hash tables. Note that SCHEME_hash_weak_ptr supplied as the initial type makes keys weak even if the hash and comparison functions are changed.

See scheme_bucket_from_table for information on buckets.

Sets the current value for *key* in *table* to *val*. If *const* is non-zero, the value for *key* must never be changed.

Sets the current value for key in table to val, but only if key is already mapped in the table.

Returns the current value for key in table, or NULL if key has no value.

Returns the bucket for key in table. The Scheme_Bucket structure is defined as:

```
typedef struct Scheme_Bucket {
   Scheme_Object so; /* so.type == scheme_bucket_type */
   /* ... */
   void *key;
   void *key;
   void *val;
} Scheme_Bucket;
```

Setting *val* to NULL unmaps the bucket's key, and *key* can be NULL in that case as well. If the table holds keys weakly, then *key* points to a (weak) pointer to the actual key, and the weak pointer's value can be NULL.

Returns a fixnum value for the given floating-point number *d*. If *d* is not an integer or if it is too large, then an error message is reported; *name* is used for error-reporting.

intptr_t scheme_get_milliseconds()

Returns the current "time" in milliseconds, just like current-milliseconds.

intptr_t scheme_get_process_milliseconds()

Returns the current process "time" in milliseconds, just like current-processmilliseconds.

char* scheme_banner()

Returns the string that is used as the Racket startup banner.

char* scheme_version()

Returns a string for the executing version of Racket.

Scheme_Hash_Table* scheme_get_place_table()

Returns an eq?-based hash table that is global to the current place.

A key generated by scheme_malloc_key can be useful as a common key across multiple places.

```
Scheme_Object* scheme_malloc_key()
```

Generates an uncollectable Racket value that can be used across places. Free the value with scheme_free_key.

```
void scheme_free_key(Scheme_Object* key)
```

Frees a key allocated with scheme_malloc_key. When a key is freed, it must not be accessible from any GC-travsered reference in any place.

Gets or sets a value in a process-global table (i.e., shared across multiple places, if any). If *val* is NULL, the current mapping for *key* is given, otherwise *val* is installed as the value for *key* and NULL is returned. The given *val* must not refer to garbage-collected memory.

This function is intended for infrequent use with a small number of keys.

19 Flags and Hooks

The following flags and hooks are available when Racket is embedded:

- scheme_exit This pointer can be set to a function that takes an integer argument and returns void; the function will be used as the default exit handler. The default is NULL.
- scheme_make_stdin, scheme_make_stdout, scheme_make_stderr, These pointers can be set to a function that takes no arguments and returns a Racket port Scheme_Object * to be used as the starting standard input, output, and/or error port. The defaults are NULL. Setting the initial error port is particularly important for seeing unexpected error messages if stderr output goes nowhere.
- scheme_console_output This pointer can be set to a function that takes a string and a intptr_t string length; the function will be called to display internal Racket warnings and messages that possibly contain non-terminating nuls. The default is NULL.
- scheme_check_for_break This points to a function of no arguments that returns an integer. It is used as the default user-break polling procedure in the main thread. A non-zero return value indicates a user break, and each time the function returns a nonzero value, it counts as a new break signal (though the break signal may be ignored if a previous signal is still pending). The default is NULL.
- scheme_case_sensitive If this flag is set to a non-zero value before scheme_basic_env is called, then Racket will not ignore capitalization for symbols and global variable names. The value of this flag should not change once it is set. The default is zero.
- scheme_allow_set_undefined This flag determines the initial value of compile-allow-set!-undefined. The default is zero.
- scheme_console_printf This function pointer was left for backward compatibility. The default builds a string and calls scheme_console_output.

void scheme_set_collects_path(Scheme_Object* path)

Sets the path to be returned by (find-system-path 'collects-dir).

void scheme_set_addon_path(Scheme_Object* path)

Sets the path to be returned by (find-system-path 'addon-dir).

Initializes the current-library-collection-paths parameter using find-library-collection-paths. The *pre_extra_paths* and *post_extra-paths* arguments are propagated to find-library-collection-paths.

The function calls scheme_seal_parameters automatically.

```
void scheme_init_collection_paths(Scheme_Env* env,
Scheme_Object* pre_extra_paths)
```

Like scheme_init_collection_paths_post, but with null as the last argument.

void scheme_seal_parameters()

Takes a snapshot of the current values of built-in parameters. These values are used for privileged actions, such as installing a PLaneT package.

Index

```
"escheme.h",6
"libmzgc.a",10
"libmzgc.la",10
"libmzgc.so", 10
"libracket.a",10
"libracket.la",10
"libracket.so",10
"libracket3m.a",13
"libracket3m.la",13
"libracket3m.so",13
"mzdyn.o",7
"mzdyn.obj",7
"mzdyn3m.o",8
"mzdyn3m.obj",8
"Scheme" versus "Racket", 5
"scheme.h",10
#%variable-reference, 51
--3m, 8
--cc, 6
--cgc, 6
--1d.7
--xform.8
3m, 5
3m Embedding, 13
3m Extensions, 8
_scheme_apply, 60
_scheme_apply_multi, 60
_scheme_eval_compiled, 59
_scheme_eval_compiled_multi, 59
allocation, 7
allocation, 11
Allowing Thread Switches, 74
arity, 54
Bignums, Rationals, and Complex Numbers,
 96
Blocking the Current Thread, 74
Building Racket from Source, 5
Callbacks for Blocked Threads, 76
CGC, 5
CGC Embedding, 10
```

CGC Extensions, 6 CGC versus 3m, 5 Continuation Marks, 90 continuations, 63 Cooperating with 3m, 32 current working directory, 114 Custodians, 120 Declaring a Module in an Extension, 9 embedding Racket, 10 Embedding Racket into a Program, 10 Enabling and Disabling Breaks, 67 Evaluation, 57 **Evaluation Functions**, 59 **Exception Functions**, 67 Exceptions and Escape Continuations, 63 extending Racket, 5 Flags and Hooks, 130 fork, 123 garbage collection, 31 GC_fixup_self, 48 GC_register_traversers, 48 GC resolve, 48 Global Constants, 22 globals, in extension code, 32 globals, 51 Guiding raco ctool --xform, 39 header files, 6 Inside: Racket C API, 1 Integers, 17 Integration with Threads, 73 Local Pointers, 34 Local Pointers and raco ctool --xform, 38 master, 41 memory, 31 Memory Allocation, 31 Memory Functions, 41 Miscellaneous Utilities, 124 module, 51 Multiple Values, 58 MZ_GC_ARRAY_VAR_IN_REG, 35 MZ_GC_DECL_REG, 35

Procedures, 54 MZ_GC_NO_VAR_IN_REG, 37 MZ_GC_REG, 36 MZ_GC_UNREG, 35 MZ_GC_VAR_IN_REG, 35 MZCONFIG_ALLOW_SET_UNDEFINED, 87 raco ctool, 6 MZCONFIG_CAN_READ_BOX, 86 MZCONFIG_CAN_READ_COMPILED, 86 MZCONFIG_CAN_READ_GRAPH, 86 MZCONFIG_CAN_READ_PIPE_QUOTE, 86 MZCONFIG_CASE_SENS, 87 MZCONFIG COLLECTION PATHS, 87 MZCONFIG_CURLY_BRACES_ARE_PARENS, 87 MZCONFIG_CUSTODIAN, 87 MZCONFIG_ENV, 86 MZCONFIG_ERROR_DISPLAY_HANDLER, 86 MZCONFIG ERROR PORT, 86 MZCONFIG_ERROR_PRINT_VALUE_HANDLER, 121 86 MZCONFIG_ERROR_PRINT_WIDTH, 87 MZCONFIG_EVAL_HANDLER, 86 47 MZCONFIG_EXIT_HANDLER, 86 MZCONFIG_INIT_EXN_HANDLER, 86 MZCONFIG_INPUT_PORT, 86 MZCONFIG_LOAD_DIRECTORY, 87 MZCONFIG_LOAD_EXTENSION_HANDLER, 87 MZCONFIG_LOAD_HANDLER, 86 MZCONFIG_OUTPUT_PORT, 86 MZCONFIG_PORT_PRINT_HANDLER, 87 MZCONFIG_PRINT_BOX, 87 MZCONFIG_PRINT_GRAPH, 86 MZCONFIG_PRINT_HANDLER, 86 MZCONFIG_PRINT_STRUCT, 87 MZCONFIG_PROMPT_READ_HANDLER, 86 MZCONFIG_SQUARE_BRACKETS_ARE_PARENS, scheme_apply_to_list, 60 87 MZCONFIG_USE_COMPILED_KIND, 87 Namespaces and Modules, 51 Overview, 5 Parameterizations, 86 Places and Garbage Collector Instances, 41 Ports and the Filesystem, 99 scheme_bignum_to_float, 96

Racket and Places, 15 Racket and Threads, 16 Racket, Unicode, Characters, and Strings, 16 scheme_add_atexit_closer, 121 scheme_add_evt, 83 scheme_add_evt_through_sema, 84 scheme_add_fd_eventmask, 83 scheme_add_fd_handle,83 scheme_add_finalizer,46 scheme_add_finalizer_once, 47 scheme_add_gc_callback, 49 scheme_add_global, 51 scheme_add_global_symbol, 51 scheme_add_managed, 120 scheme_add_managed_close_on_exit, scheme_add_scheme_finalizer, 47 scheme_add_scheme_finalizer_once, scheme_add_swap_callback, 85 scheme_add_swap_out_callback, 85 scheme_add_to_table, 128 scheme_alloc_byte_string, 25 scheme_alloc_char_string, 26 scheme_alloc_flvector, 28 scheme_alloc_fxvector, 28 scheme_allow_set_undefined, 130 scheme_append, 125 scheme_append_byte_string, 25 scheme_append_char_string, 27 scheme_apply, 60 scheme_apply_multi, 60 scheme_banner, 129 scheme_basic_env, 59 scheme_bignum_from_double, 96 scheme_bignum_from_float, 97 scheme_bignum_normalize, 97 scheme_bignum_to_double, 96

scheme_bignum_to_string, 97 scheme_char_string_to_byte_string, 27 scheme_bignum_type, 19 SCHEME_BIGNUMP, 19 27 scheme_block_until, 81 scheme_block_until_enable_break, 82 scheme_block_until_unless, 82 scheme_bool_type, 19 SCHEME BOOLP, 19 scheme_char_type, 19 scheme_box, 28 SCHEME_CHAR_VAL, 19 scheme_box_type, 20 SCHEME_CHARP, 19 SCHEME BOX VAL, 20 SCHEME_BOXP, 20 scheme_break_thread, 81 scheme_break_waiting, 81 scheme_bucket_from_table, 128 scheme_bucket_table_type, 21 SCHEME_BUCKTP, 21 scheme_build_list, 125 scheme_build_mac_filename, 114 115 scheme_builtin_value, 52 scheme_byte_ready, 103 SCHEME BYTE STR VAL, 19 scheme_compile, 61 scheme_byte_string_to_char_string, 27 scheme_byte_string_to_char_string_lo&aheme_complex_imaginary_part,98 27 scheme_byte_string_type, 19 SCHEME_BYTE_STRINGP, 19 SCHEME_BYTE_STRLEN_VAL, 19 SCHEME_COMPLEXP, 19 scheme_caddr, 125 scheme_cadr, 125 scheme_call_enable_break, 84 scheme_cont_type, 21 scheme_calloc, 42 SCHEME_CAR, 20 scheme_car, 125 scheme_case_closure_type, 21 SCHEME_CPTR_TYPE, 21 scheme_case_sensitive, 130 SCHEME_CPTR_VAL, 21 SCHEME_CDR, 20 SCHEME_CPTRP, 21 scheme_cdr, 125 scheme_change_in_table, 128 scheme_char_ready, 103 72 SCHEME_CHAR_STR_VAL, 19

scheme_char_string_to_byte_string_locale, scheme_char_string_to_path, 113 scheme_char_string_type, 19 SCHEME_CHAR_STRINGP, 19 SCHEME_CHAR_STRLEN_VAL, 19 scheme_check_for_break, 130 scheme_check_proc_arity,71 scheme_check_threads, 82 scheme_clear_escape, 71 scheme_close_input_port, 104 scheme_close_managed, 121 scheme_close_output_port, 104 scheme_close_should_force_port_closed, scheme_closed_prim_type, 21 scheme_collect_garbage, 48 scheme_compiled_closure_type, 21 scheme_complex_izi_type, 19 SCHEME_COMPLEX_IZIP, 19 scheme_complex_real_part,98 scheme_complex_type, 19 scheme_console_output, 130 scheme_console_printf, 130 scheme_contract_error, 70 scheme_count_lines, 103 scheme_cpointer_type, 21 scheme_current_argument_stack, 56 scheme_current_continuation_marks,

scheme_custodian_check_available, 121 SCHEME_DBL_VAL, 19 SCHEME_DBLP, 19 scheme_debug_print, 101 scheme_detach_multiple_array, 61 scheme_directory_exists, 112 scheme_display, 99 scheme_display_to_string, 101 scheme_display_to_string_w_max, 101 scheme_display_w_max, 99 scheme_dont_gc_ptr, 47 scheme_double_to_int, 128 scheme_double_type, 19 scheme_dynamic_require, 126 scheme_dynamic_wind, 71 scheme_enable_garbage_collection, 48 scheme_end_atomic, 85 scheme_end_atomic_no_swap, 85 scheme_end_stubborn_change, 42 scheme_eof, 22 SCHEME_EOFP, 22 scheme_eq, 124 scheme_equal, 124 scheme_equal_hash_key, 124 scheme_equal_hash_key2, 124 scheme_eqv, 124 scheme_escaping_cont_type, 21 scheme_eval, 59 scheme_eval_compiled, 59 scheme_eval_compiled_multi, 59 scheme_eval_string, 60 scheme_eval_string_all, 61 scheme_eval_string_multi, 60 SCHEME_EXACT_INTEGERP, 22 SCHEME_EXACT_REALP, 22 scheme_exit, 130 scheme_expand, 61 scheme_expand_filename, 112 scheme_expand_string_filename, 113 scheme_extend_config, 88

scheme_false, 22 SCHEME_FALSEP, 22 scheme_file_exists, 112 scheme_finish_primitive_module, 53 scheme_float_type, 19 SCHEME_FLOAT_VAL, 19 SCHEME_FLOATP, 22 SCHEME_FLT_VAL, 19 SCHEME_FLTP, 19 scheme_flush_output, 101 SCHEME FLVEC ELS, 20 SCHEME_FLVEC_SIZE, 20 scheme_flvector_type, 20 SCHEME_FLVECTORP, 20 scheme_format, 114 scheme_format_utf8, 115 scheme_free_code, 43 scheme_free_immobile_box, 43 scheme_free_key, 129 scheme_fxvector_type, 20 SCHEME_FXVECTORP, 20 scheme_gc_ptr_ok, 48 scheme_get_byte, 101 scheme_get_byte_string, 102 scheme_get_byte_string_output, 111 scheme_get_bytes, 103 scheme_get_char_string, 102 scheme_get_env, 52 scheme_get_fdset, 82 scheme_get_int_val, 24 scheme_get_long_long_val, 24 scheme_get_milliseconds, 129 scheme_get_param, 87 scheme_get_place_table, 129 scheme_get_port_fd, 104 scheme_get_port_file_descriptor, 104scheme_get_port_socket, 104 scheme_get_process_milliseconds, 129 scheme_get_sized_byte_string_output, 112

scheme_get_thread_param, 88 scheme_get_unsigned_int_val, 24 scheme_get_unsigned_long_long_val, 24 scheme_getc, 101 scheme_global_bucket, 52 scheme_hash_get, 127 scheme_hash_set, 127 scheme_hash_table_type, 21 SCHEME_HASHTP, 21 scheme_inherit_cells, 88 scheme_init_collection_paths, 131 scheme_init_collection_paths_post, 130 SCHEME_INPORT_VAL, 20 SCHEME_INPORTP, 20 scheme_input_port_record, 112 scheme_input_port_type, 20 SCHEME_INPUT_PORTP, 20 scheme_install_config, 88 SCHEME_INT_VAL, 19 scheme_integer_type, 19 scheme_intern_exact_char_keyword, 28 scheme_intern_exact_char_symbol, 27 scheme_intern_exact_keyword, 28 scheme_intern_exact_symbol, 27 scheme_intern_symbol, 27 SCHEME_INTP, 19 scheme_is_exact, 96 scheme_is_inexact, 96 scheme_is_struct_instance, 117 SCHEME_KEYWORD_LEN, 20 scheme_keyword_type, 20 SCHEME_KEYWORD_VAL, 20 SCHEME_KEYWORDP, 20 scheme_list_length, 125 scheme_list_to_vector, 125 scheme_load, 126 scheme_load_extension, 126 scheme_lookup_global, 52 scheme_lookup_in_table, 128

scheme_mac_path_to_spec, 114 scheme_main_setup, 43 scheme_main_stack_setup, 44 scheme_make_arg_lines_string, 70 scheme_make_args_string, 70 scheme_make_ascii_character, 23 scheme_make_bignum, 96 scheme_make_bignum_from_unsigned, 96 scheme_make_bucket_table, 127 scheme_make_byte_string, 25 scheme_make_byte_string_input_port, 111 scheme_make_byte_string_output_port, 111 scheme_make_byte_string_without_copying, 25 scheme_make_char, 23 scheme_make_char_or_null, 23 scheme_make_char_string, 26 scheme_make_char_string_without_copying, 26 scheme_make_character, 23 scheme_make_closed_prim, 56 scheme_make_closed_prim_w_arity, 55 scheme_make_complex, 98 scheme_make_cptr, 28 scheme_make_custodian, 120 scheme_make_double, 24 scheme_make_exact_symbol, 27 scheme_make_external_cptr, 29 scheme_make_fd_input_port, 110 scheme_make_fd_output_port, 111 scheme_make_file_input_port, 110 scheme_make_file_output_port, 110 scheme_make_float, 24 scheme_make_folding_prim, 55 scheme_make_hash_table, 126 scheme_make_hash_table_equal, 127 scheme_make_input_port, 104 scheme_make_integer, 23 scheme_make_integer_value, 23

scheme_make_integer_value_from_long_hallsmes_make_stdout, 130 23 scheme_make_struct_instance, 117 scheme_make_integer_value_from_long_**iong**me_make_struct_names, 117 23 scheme_make_struct_type, 116 scheme_make_integer_value_from_unsigned_eme_make_struct_values, 117 23 scheme_make_symbol, 27 scheme_make_integer_value_from_unsigned_lengake_tfifead_cell,85 24 scheme_make_type, 28 scheme_make_integer_value_from_unsigned_long_long_tf8_string, 25 23 scheme_make_vector, 28 scheme_make_locale_string, 25 scheme_make_weak_box, 28 scheme_make_named_file_input_port, scheme_making_progress, 84 110 scheme_malloc, 41 scheme_make_namespace, 59 scheme_malloc_allow_interior, 42 scheme_make_offset_cptr, 29 scheme_malloc_atomic, 42 scheme_make_offset_external_cptr, scheme_malloc_atomic_allow_interior, 29 42 scheme_make_output_port, 107 scheme_malloc_code, 43 scheme_make_pair, 24 scheme_malloc_eternal, 42 scheme_make_path, 113 scheme_malloc_fail_ok, 43 scheme_make_path_without_copying, scheme_malloc_immobile_box, 43 113 scheme_malloc_key, 129 scheme_make_port_type, 104 scheme_malloc_stubborn, 42 scheme_make_prim, 55 scheme_malloc_tagged, 42 scheme_make_prim_closure_w_arity, scheme_malloc_uncollectable, 42 55 SCHEME_MCAR, 20 scheme_make_prim_w_arity, 54 SCHEME_MCDR, 20 scheme_make_provided_string, 70 scheme module bucket, 52 scheme make rational, 97 SCHEME_MPAIRP, 20 scheme_make_sema, 80 scheme_mutable_pair_type, 20 scheme_make_sized_byte_string, 25 scheme_namespace_require, 126 scheme_make_sized_char_string, 26 scheme_make_sized_offset_byte_string, scheme_namespace_type, 21 25 SCHEME_NAMESPACEP, 21 25 scheme_make_sized_offset_char_string, scheme_need_wakeup, 103 26 scheme_new_param, 88 scheme_make_sized_offset_path, 113 scheme_make_sized_offset_utf8_string; SCHEME_NULLP, 22 26 SCHEME_NUMBERP, 21 scheme_make_sized_path, 113 scheme_open_input_file, 110 scheme_make_sized_utf8_string, 26 scheme_open_output_file, 110 scheme_make_stderr, 130 scheme_os_getcwd, 114 scheme_make_stdin, 130

scheme_os_setcwd, 114 SCHEME_OUTPORT_VAL, 21 SCHEME_OUTPORTP, 21 scheme_output_port_record, 112 scheme_output_port_type, 21 SCHEME_OUTPUT_PORTP, 21 scheme_pair_type, 20 SCHEME PAIRP, 20 scheme_param_config, 89 SCHEME_PATH_LEN, 19 scheme_path_to_char_string, 113 scheme_path_type, 19 SCHEME_PATH_VAL, 19 SCHEME_PATHP, 19 scheme_peek_byte, 101 scheme_peek_byte_skip, 101 scheme_peekc, 101 scheme_peekc_skip, 102 scheme_pipe, 112 scheme_pipe_with_limit, 112 scheme_pop_break_enable, 72 scheme_pop_continuation_frame, 90 scheme_port_count_lines, 109 scheme_post_sema, 80 scheme_prim_type, 21 scheme_primitive_module, 52 scheme_print_bytes, 30 scheme_print_string, 30 scheme_printf, 115 scheme_printf_utf8, 115 SCHEME PROCP, 21 scheme_proper_list_length, 125 scheme_push_break_enable, 71 scheme_push_continuation_frame, 90 scheme_put_byte_string, 100 scheme_put_char_string, 100 scheme_raise_exn, 68 scheme_rational_denominator, 98 scheme_rational_from_double, 98 scheme_rational_from_float, 98 scheme_rational_numerator, 97 scheme_rational_to_double, 97

scheme_rational_to_float, 97 scheme_rational_type, 19 SCHEME_RATIONALP, 19 scheme_read, 99 scheme_read_bignum, 97 scheme_read_bignum_bytes, 97 scheme_real_to_double, 24 SCHEME REALP, 22 scheme_recur_equal, 124 scheme_recur_equal_hash_key, 124 scheme_recur_equal_hash_key2, 124 scheme_register_extension_global, 43 scheme_register_finalizer, 46 scheme_register_parameter, 88 scheme_register_process_global, 129 scheme_register_static, 45 scheme_register_tls_space, 45 scheme_remove_all_finalization, 47 scheme_remove_gc_callback, 50 scheme_remove_managed, 121 scheme_seal_parameters, 131 scheme_security_check_file, 119 scheme_security_check_network, 119 scheme_sema_type, 21 SCHEME_SEMAP, 21 scheme_set_addon_path, 130 scheme set box, 125 scheme_set_can_break,71 scheme_set_collects_path, 130 scheme_set_cont_mark, 90 scheme_set_file_position, 103 scheme_set_global_bucket, 52 scheme_set_param, 87 scheme_set_port_count_lines_fun, 109 scheme_set_port_location_fun, 109 scheme_set_stack_base, 44 scheme_set_stack_bounds, 45 scheme_set_thread_param, 88 scheme_set_type_equality, 30 scheme_set_type_printer, 29

scheme_signal_error, 67 scheme_signal_received, 82 scheme_socket_to_ports, 111 scheme_strdup, 42 scheme_strdup_eternal, 43 scheme_struct_property_type, 20 scheme_struct_ref, 118 scheme_struct_set, 118 scheme_struct_type_type, 20 SCHEME_STRUCT_TYPEP, 20 SCHEME STRUCTP, 20 scheme_structure_type, 20 scheme_subtract_finalizer,47 scheme_swap_thread, 81 SCHEME_SYM_LEN, 20 SCHEME_SYM_VAL, 20 scheme_symbol_type, 20 SCHEME_SYMBOLP, 20 scheme_tail_apply, 61 scheme_tail_apply_no_copy, 61 scheme_tail_apply_to_list, 61 scheme tell, 103 scheme_tell_line, 103 scheme_thread, 79 scheme_thread_block, 80 scheme_thread_block_enable_break, 80 scheme_thread_type, 21 scheme_thread_w_details, 80 SCHEME_THREADP, 21 scheme_tls_allocate, 84 scheme_tls_get, 84 scheme_tls_set, 84 scheme_true, 22 SCHEME_TRUEP, 22 SCHEME_TYPE, 18 scheme_ucs4_to_utf16,94 scheme_unbound_global, 69 scheme_unbox, 125 scheme_undefined, 22 scheme_ungetc, 103 scheme_utf16_to_ucs4, 94

scheme_utf8_decode, 91 scheme_utf8_decode_all, 92 scheme_utf8_decode_as_prefix, 92 scheme_utf8_decode_count, 93 scheme_utf8_decode_prefix, 92 scheme_utf8_decode_to_buffer, 92 scheme_utf8_decode_to_buffer_len, 93 scheme_utf8_encode, 93 scheme_utf8_encode_all,94 scheme_utf8_encode_to_buffer, 94 scheme_utf8_encode_to_buffer_len, 94 scheme_values, 61 SCHEME_VEC_ELS, 20 SCHEME_VEC_SIZE, 20 scheme_vector_to_list, 125 scheme_vector_type, 20 SCHEME_VECTORP, 20 scheme_version, 129 scheme_void, 22 SCHEME_VOIDP, 22 scheme_wait_sema, 80 scheme_wake_up, 82 scheme_warning, 72 scheme_weak_box_type, 21 SCHEME_WEAK_PTR, 21 scheme_weak_reference, 45 scheme_weak_reference_indirect, 46 SCHEME_WEAKP, 21 scheme_write,99 scheme_write_byte_string, 100 scheme_write_char_string, 100 scheme_write_to_string, 100 scheme_write_to_string_w_max, 101 scheme_write_w_max, 99 scheme_wrong_contract, 69 scheme_wrong_count, 68 scheme_wrong_return_arity, 69 scheme_wrong_type, 69 Security Guards, 119 SIGCHLD, 123

Sleeping by Embedded Racket, 78 Standard Types, 19 String Encodings, 91 strings, conversion to C, 19 strings, conversion to C, 19 Strings, 22 Structures, 116 Subprocesses, 123 sync, 75 Tagged Objects, 33 Tail Evaluation, 57 tail recursion, 57 Temporarily Catching Error Escapes, 64 Thread Functions, 79 Threads, 73 Threads in Embedded Racket with Event Loops, 75 Top-level Evaluation Functions, 57 types, creating, 18 Value Functions, 23 Values and Types, 18 waitpid, 123 Writing Racket Extensions, 5 XFORM_CAN_IGNORE, 41 XFORM_END_SKIP, 40 XFORM_END_SUSPEND, 41 XFORM_END_TRUST_ARITH, 41 XFORM_HIDE_EXPR, 40 XFORM_SKIP_PROC, 40 XFORM_START_SKIP, 40 XFORM_START_SUSPEND, 41 XFORM_START_TRUST_ARITH, 41 XFORM_TRUST_MINUS, 41 XFORM_TRUST_PLUS, 41