Readline: Terminal Interaction

Version 5.3

August 6, 2012

The "readline" collection (not to be confused with Racket's read-line function) provides glue for using GNU's Readline library with the Racket read-eval-print-loop.

1 Normal Use of Readline

```
(require readline)
(require readline/rep-start)
```

The readline library installs a Readline-based input port (whose name is 'readline-input) and hooks the prompt-and-read part of Racket's read-eval-print-loop to interact with it.

You can start Racket with

racket -il readline

or evaluate

```
(require readline)
```

in the Racket read-eval-print-loop to load Readline manually. You can also put (require readline) in your "~/.racketrc", so that Racket automatically loads Readline support in interactive mode.

If you want to enable Readline support only sometimes—such as only when you use an xterm, and not when you use an Emacs shell—then you can use dynamic-require, as in the following example:

The readline library automatically checks whether the current input port is a terminal, as determined by terminal-port?, and it installs Readline only to replace terminal ports. The readline/rep-start module installs Readline without a terminal check.

By default, Readline's completion is set to use the visible bindings in the current namespace. This is far from ideal, but it's better than Readline's default filename completion which is rarely useful. In addition, the Readline history is stored across invocations in Racket's preferences file, assuming that Racket exits normally.

The readline library adjusts read-eval-print-loop by setting the prompt read handler as determined by current-prompt-read. The call to the read interaction handler (as determined by current-read-interaction) is parameterized to set readline-prompt, so that a prompt will be printed when reading starts. To compensate for the prompt printed via readline-prompt, when the interaction input port's name (as produced by function in the current-get-interaction-input-port parameter) is 'readline-input, the prompt read handler skips printing a prompt; otherwise, it displays a prompt as determined by current-prompt.

(install-readline!) \rightarrow void?

Adds (require readline/rep) to the result of (find-system-path 'init-file), which is "~/.racketrc" on Unix. Consequently, Readline will be loaded whenever Racket is started in interactive mode. The declaration is added only if it is not already present, as determined by reading and checking all top-level expressions in the file.

For more fine-grained control, such as conditionally loading Readline based on an environment variable, edit " \sim /.racketrc" manually.

2 Interacting with the Readline-Enabled Input Port

(require readline/pread)

The readline/pread library provides customization, and support for prompt-reading after readline installs the new input port.

The reading facility that the new input port provides can be customized with the following parameters.

```
(current-prompt) → bytes?
(current-prompt bstr) → void?
bstr : bytes?
```

A parameter that determines the prompt that is used, as a byte string. Defaults to #"> ".

```
(max-history) → exact-nonnegative-integer?
(max-history n) → void?
n : exact-nonnegative-integer?
```

A parameter that determines the number of history entries to save, defaults to 100.

```
(keep-duplicates) → (one-of/c #f 'unconsecutive #t)
(keep-duplicates keep?) → void?
  keep? : (one-of/c #f 'unconsecutive #t)
```

A parameter. If #f (the default), then when a line is equal to a previous one, the previous one is removed. If it set to 'unconsecutive then this happens only for an line that duplicates the previous one, and if it is #f then all duplicates are kept.

```
(keep-blanks) → boolean?
(keep-blanks keep?) → void?
keep? : any/c
```

A parameter. If #f (the default), blank input lines are not kept in history.

```
(readline-prompt) → (or/c false/c bytes? (one-of/c 'space))
(readline-prompt status) → void?
  status : (or/c false/c bytes? (one-of/c 'space))
```

The new input port that you get when you require readline is a custom port that uses Readline for all inputs. The problem is when you want to display a prompt and then read some input, Readline will get confused if it is not used when the cursor is at the beginning of the line (which is why it has a *prompt* argument.) To use this prompt:

```
(parameterize ([readline-prompt some-byte-string])
   ...code-that-reads...)
```

This expression makes the first call to Readline use the prompt, and subsequent calls will use an all-spaces prompt of the same length (for example, when you're reading an S-expression). The normal value of readline-prompt is #f for an empty prompt (and spaces after the prompt is used, which is why you should use parameterize to restore it to #f).

A proper solution would be to install a custom output port, too, which keeps track of text that is displayed without a trailing newline. As a cheaper solution, if line-counting is enabled for the terminal's output-port, then a newline is printed before reading if the column is not 0. (The readline library enables line-counting for the output port.)

Warning: The Readline library uses the output port directly. You should not use it when current-input-port has been modified, or when it was not a terminal port when Racket was started (eg, when reading input from a pipe). Expect some problems if you ignore this warning (not too bad, mostly problems with detecting an EOF).

3 Direct Bindings for Readline Hackers

(require readline/readline)

```
(readline prompt) → string?
prompt : string?
```

Prints the given prompt string and reads a line.

```
(readline-bytes prompt) → bytes?
prompt : bytes?
```

Like readline, but using raw byte-strings for the prompt and returning a byte string.

```
(add-history str) \rightarrow void?
str : string?
```

Adds the given string to the Readline history, which is accessible to the user via the up-arrow key.

```
(add-history-bytes str) → void?
  str : bytes?
```

Adds the given byte string to the Readline history, which is accessible to the user via the up-arrow key.

```
(history-length) \rightarrow exact-nonnegative-integer?
```

Returns the length of the history list.

```
(history-get idx) \rightarrow string?
idx : integer?
```

Returns the history string at the idx position. idx can be negative, which will make it count from the last (i.e, -1 returns the last item, -2 returns the second-to-last, etc.)

```
(history-delete idx) \rightarrow string?
idx : integer?
```

Deletes the history string at the idx position. The position is specified in the same way as the argument for history-get.

Sets Readline's rl_completion_entry_function to *proc*. The *type* argument, whose possible values are from ffi/unsafe, determines the type of value supplied to the *proc*.

4 License Issues

GNU's Readline library is covered by the GPL, and that applies to code that links with it. Racket is licensed with the LGPL, so the Readline code is not used by default; you should explicitly enable it if you want to. Also, be aware that if you write code that uses this library, it will make your code link to the Readline library when invoked, with the usual GPL implications.