

SASL: Simple Authentication and Security Layer

Version 7.6

Ryan Culpepper <ryanc@racket-lang.org>

February 12, 2020

This library provides implementations of some SASL (RFC 4422) mechanisms. Currently only client support is implemented; future versions of this library may add server support.

1 SASL Introduction

This library implements non-trivial (multi-message) authentication mechanisms using *SASL protocol contexts*. Since in general SASL is embedded as a sub-protocol of some application protocol, this library does not handle I/O directly. Instead, the user is responsible for transferring messages between the SASL context and the application protocol.

Note that some SASL authentication mechanisms leave the communication of authentication success or failure to the application layer. Even when a mechanism normally communicates the result of authentication, some applications choose to convey failure at the application layer.

The following is a sketch of a typical embedding of SASL in an application protocol:

1. server → client: ... Hello. I understand the following SASL mechanisms: SCRAM-SHA-1 and CRAM-MD5
2. client → server: I choose SCRAM-SHA-1. My initial SASL message is “<initial *SCRAM-SHA-1 message*>”.
3. server → client: My SASL response is “<*SCRAM-SHA-1 response*>”.
4. client → server: My final SASL message is “final <*SCRAM-SHA-1 message*>”.
5. server → client: My final SASL response is “<final *SCRAM-SHA-1 response*>”.
6. client → server: Great! Let’s get to work....

In particular, the application layer advertises and selects SASL mechanisms, embeds SASL messages using some application-specific framing, and resumes after authentication is complete.

2 SASL Protocol Contexts

```
(require sasl)      package: sasl-lib
```

```
(sasl-ctx? v) → boolean?  
  v : any/c
```

Returns `#t` if `v` is a SASL protocol context, `#f` otherwise.

```
(sasl-next-message ctx) → (or/c string? bytes?)  
  ctx : sasl-ctx?
```

Returns the next outgoing message to be sent. Subsequent calls to `sasl-next-message` return the same message until the outgoing message is updated after a call to `sasl-receive-message`.

This function may be called only when `(sasl-state ctx)` is `'send/receive` or `'send/done`; otherwise, an exception is raised.

```
(sasl-receive-message ctx message) → void?  
  ctx : sasl-ctx?  
  message : (or/c string? bytes?)
```

Update the SASL context with a newly received `message`.

If `message` represents progress or success, then `ctx` is updated and subsequent calls to `sasl-next-message` return a new message (or fail, if the protocol is done).

If `message` indicates authentication failure or if `message` is ill-formed or invalid, an exception is raised and `ctx` enters a permanent error state (see `sasl-state`). The user must take appropriate action after either kind of failure. For example, upon authentication failure the client might close the connection and try again with different credentials.

This function may be called only when `(sasl-state ctx)` is `'receive` or `'send/receive`; otherwise, an exception is raised.

```
(sasl-state ctx)  
→ (or/c 'receive 'send/receive 'send/done 'done 'error)  
  ctx : sasl-ctx?
```

Returns a symbol indicating the state that `ctx` is in with respect to its protocol. The number of states is due to the following factors: the initial SASL message may be sent from the client or the server (depending on the mechanism); the final SASL message may be sent from the client or the server (depending on the mechanism); and the SASL context doesn't know whether an outgoing message has been forwarded to the application layer and sent.

The possible states consist of the following:

- `'receive'`: the protocol starts with `ctx` receiving a message
- `'send/receive'`: send the current outgoing message (`sasl-next-message`) if it hasn't already been sent, then receive
- `'send/done'`: send the current outgoing message (`sasl-next-message`) if it hasn't already been sent, then the SASL protocol is done
- `'done'`: the SASL protocol ended with the last received message
- `'error'`: a fatal error occurred

3 SASLprep

```
(require sasl/saslprep)      package: sasl-lib

(saslprep s
  [#:allow-unassigned? allow-unassigned?]) → string?
  s : string?
  allow-unassigned? : boolean? = #f
```

Implements the SASLprep (RFC 4013) algorithm for preparing user names and passwords for comparison, hashing, etc.

In general, the mechanism implementations in this library call `saslprep` on their arguments when appropriate.

4 SCRAM Authentication

(require `sasl/scram`) package: `sasl-lib`

This module implements the SCRAM family of authentication mechanisms, namely SCRAM-SHA-1 and SCRAM-SHA-256. The `-PLUS` variants, which add channel binding, are not implemented.

The SCRAM protocol family has the following structure:

1. client → server: initial message with nonce prefix
2. server → client: reply with complete nonce and PBKDF2 salt and iteration count
3. client → server: client signature
4. server → client: authentication result and server signature

In particular: the client sends the first message; authentication success or failure is conveyed at in SASL protocol layer; and the server authenticates itself to the client. Messages are represented as strings.

```
(make-scram-client-ctx digest
                      authentication-id
                      password
                      [#:authorization-id authorization-id])
→ sasl-ctx?
digest : (or/c 'sha1 'sha256)
authentication-id : string?
password : string?
authorization-id : (or/c string? #f) = #f
```

Creates a SCRAM protocol context. The *digest* argument selects between SCRAM-SHA-1 and SCRAM-SHA-256. The *authentication-id*, *password*, and (if provided) *authorization-id* arguments are automatically processed using `saslprep`.

5 CRAM-MD5 Authentication

```
(require sasl/cram-md5)    package: sasl-lib
```

This module implements the CRAM-MD5 authentication mechanism.

The CRAM-MD5 protocol has the following structure:

- server → client: challenge
- client → server: response

In particular, the server sends the first message, and the server communicates authentication success or failure at the application protocol layer. Messages are represented as strings.

```
(make-cram-md5-client-ctx authentication-id  
                          password)    → sasl-ctx?  
authentication-id : string?  
password : string?
```

Creates a CRAM-MD5 protocol context. The *authentication-id* and *password* arguments are automatically processed using [saslprep](#).

6 PLAIN Authentication

```
(require sasl/plain)    package: sasl-lib
```

This module implements the PLAIN mechanism.

Since the PLAIN mechanism consists of a single message from the client to the server, it is implemented as a simple procedure rather than a SASL protocol context. The authentication outcome is conveyed at the application protocol layer.

```
(plain-client-message authentication-id
                      password
                      [#:authorization-id authorization-id])
→ string?
authentication-id : string?
password : string?
authorization-id : (or/c string? #f) = #f
```

Constructs a PLAIN client message containing the *authentication-id*, *password*, and (if present) *authorization-id*. The arguments are automatically processed with `saslprep`.